

Software Analyzers

Developer Manual





Plug-in Development Guide

Release 24.0-beta (Chromium)

Julien Signoles with Thibaud Antignac, Loïc Correnson, Matthieu Lemerre and Virgile Prevosto

This work is licensed under a Creative Commons "Attribution-ShareAlike 4.0 International" license.



CEA-List, Université Paris-Saclay Software Safety and Security Lab

02009-2021 CEA LIST



Contents

Fo	Foreword 9						
1	1 Introduction						
	1.1	About	this document	11			
	1.2	Outlin	ne	12			
2	Tutorial 1						
	2.1	Quick Setup of a Development Environment					
		2.1.1	Emacs Configuration Files	13			
		2.1.2	Quick Merlin guide	14			
	2.2	What	Does a Plug-in Look Like?	14			
	2.3	The H	Iello plug-in	15			
		2.3.1	A Simple Script	15			
		2.3.2	Registering a Script as a Plug-in	16			
		2.3.3	Displaying Messages	17			
		2.3.4	Adding Command Line Options	18			
		2.3.5	Writing a Makefile	19			
		2.3.6	Testing your Plug-in	22			
		2.3.7	Documenting your Source Code	24			
	2.4	The V	/iewCfg plug-in	26			
		2.4.1	Visiting the AST	26			
		2.4.2	Plug-In registration and command-line options	29			
		2.4.3	Interfacing with a kernel-integrated plug-in	30			
		2.4.4	Extending the Frama-C GUI	31			
		2.4.5	Splitting files and writing a Makefile	33			
		2.4.6	Getting your Plug-in Usable by Others	36			
		2.4.7	Writing your Plug-in into the Journal	36			
		2.4.8	Writing a Configure Script	36			
		2.4.9	Getting your plug-in Usable in a Multi Projects Setting	37			

CONTENTS

3	3 Software Architecture				
	3.1	Gener	al Description	41	
	3.2	Plug-i	ns	43	
	3.3	Librar	ries	43	
	3.4	Kerne	l Services	43	
	3.5	Kerne	l Internals	44	
4	Adv	vanced	Plug-in Development	45	
	4.1	Frama	-C Configure.in	45	
		4.1.1	Principle	46	
		4.1.2	Addition of a Simple Plug-in	46	
		4.1.3	Configuration of New Libraries or Tools	47	
		4.1.4	Addition of Library/Tool Dependencies	48	
		4.1.5	Addition of Plug-in Dependencies	49	
	4.2	Plug-i	n Specific Configure.ac	49	
	4.3	Frama	-C Makefile	50	
	4.4	Plug-i	n Specific Makefile	51	
		4.4.1	Using Makefile.dynamic	51	
		4.4.2	Compiling Frama-C and external plug-ins at the same time $\hfill \ldots \hfill \ldots$	52	
	4.5	Testin	g	52	
		4.5.1	Using ptests	53	
		4.5.2	Configuration	54	
		4.5.3	Alternative Testing	55	
		4.5.4	Detailed options	56	
		4.5.5	Detailed directives	57	
	4.6 Plug-in General Services		n General Services	60	
	4.7 Logging Services		ng Services	61	
		4.7.1	From printf to Log	62	
		4.7.2	Log Quick Reference	62	
		4.7.3	Logging Routine Options	63	
		4.7.4	Advanced Logging Services	65	
	4.8	The D	atatype library: Type Values and Datatypes	67	
		4.8.1	Type Value	67	
		4.8.2	Datatype	68	
	4.9	Plug-i	n Registration and Access	71	
		4.9.1	Registration through a .mli File	72	
		4.9.2	Kernel-integrated Registration and Access	72	
		4.9.3	Dynamic Registration and Access	74	

CONTENTS

	4.10	Journalization	7
	4.11	Project Management System	7
		4.11.1 Overview and Key Notions	7
		4.11.2 State: Principle	7
		4.11.3 Registering a New State	79
		4.11.4 Direct Use of Low-level Functor State_builder.Register 8	31
		4.11.5 Using Projects	33
		4.11.6 Selections	84
	4.12	Command Line Options	35
		4.12.1 Definition	35
		4.12.2 Tuning	86
	4.13	Initialization Steps	87
	4.14	Customizing the AST creation	39
	4.15	Customizing the machine model	90
	4.16	Machdep record fields	96
	4.17	Visitors	98
		4.17.1 Entry Points	99
		4.17.2 Methods	99
		4.17.3 Action Performed	99
		4.17.4 Visitors and Projects	0
		4.17.5 In-place and Copy Visitors	0
		4.17.6 Differences Between the Cil and Frama-C Visitors)1
		4.17.7 Example)1
	4.18	Logical Annotations	12
	4.19	Extending ACSL annotations)3
	4.20	Locations)7
		4.20.1 Representations	18
		4.20.2 Map Indexed by Locations 10	18
	4.21	GUI Extension	18
	4.22	Documentation	19
		4.22.1 General Overview	19
		4.22.2 Source Documentation	19
5 Reference Manual		erence Manual 11	3
	5.1	Configure.in	
	5.2	Makefiles 11	
	.	5.2.1 Overview	
			-

CONTENTS

		5.2.2	$Sections \ of \ {\tt Makefile}, \ {\tt Makefile}. {\tt generating}, \ {\tt Makefile}. {\tt config.in},$			
			Makefile.common and Makefile.generic	116		
		5.2.3	Variables of Makefile.dynamic	119		
		5.2.4	.Makefile.user	123		
		5.2.5	Makefile.dynamic	125		
	5.3	Ptests		125		
		5.3.1	Pre-defined macros for tests commands	125		
	5.4	Profili	ng with Landmarks	125		
A	Cha	nges		127		
Bibliography List of Figures						

Foreword

This is the documentation of the Frama-C implementation¹ which aims at helping developers integrate new plug-ins inside this platform. It started as a deliverable of the task 2.3 of the ANR RNTL project CAT^2 .

The content of this document corresponds to the version 24.0-beta (Chromium), released on November 4, 2021, of Frama-C. However the development of Frama-C is still ongoing: features described here may still evolve in the future.

Acknowledgements

We gratefully thank all the people who contributed to this document: Michele Alberti, Gergö Barany, Patrick Baudin, Allan Blanchard, Richard Bonichon, David Bühler, Pascal Cuoq, Zaynah Dargaye, Basile Desloges, Florent Garnier, Pierre-Loïc Garoche, Philippe Herrmann, Boris Hollas, Nikolaï Kosmatov, Jean-Christophe Léchenet, Romain Maliach-Auguste, André Maroneze, Benjamin Monate, Yannick Moy, Anne Pacalet, Valentin Perrelle, Armand Puccetti, Muriel Roger and Boris Yakobowski.

We also thank Johannes Kanig for his Mlpost support³, the tool formerly used for making figures of this document.

¹http://frama-c.com

²http://www.rntl.org/projet/resume2005/cat.htm

³http://mlpost.lri.fr



Chapter 1 Introduction

Frama-C (Framework for Modular Analyses of C) is a software platform which helps the development of static analysis tools for C programs thanks to a plug-ins mechanism.

This guide aims at helping developers program within the Frama-C platform, in particular for developing a new analysis or a new source-to-source transformation through a new plug-in. For this purpose, it provides a step-by-step tutorial, a general presentation of the Frama-C software architecture, a set of Frama-C-specific programming rules and an overview of the API of the Frama-C kernel. However it does not provide a complete documentation of the Frama-C plug-ins. This API and, in particular, it does not describe the API of existing Frama-C plug-ins. This API is documented in the html source code generated by make doc (see Section 4.22.1 for additional details about this documentation).

This guide introduces neither the use of Frama-C which is the purpose of the user manual [3] and of the reference articles [7, 12], nor the use of plug-ins which are documented in separated and dedicated manuals [2, 4, 9, 11, 19]. We assume that the reader of this guide already read the Frama-C user manual and knows the main Frama-C concepts.

The reader of this guide may be either a Frama-C beginner who just finished reading the user manual and wishes to develop his/her own analysis with the help of Frama-C, an intermediate-level plug-in developer who would like to have a better understanding of one particular aspect of the framework, or a Frama-C expert who wants to remember details about one specific point of the Frama-C development.

Frama-C is fully developed within the OCaml programming language [13]. Motivations for this choice are given in a Frama-C experience report [8]. However this guide *does not* provide any introduction to this programming language: the World Wide Web already contains plenty of resources for OCaml developers (see for instance https://ocaml.org/).

1.1 About this document

To ease reading, section heads may state the category of readers they are intended for and a set of prerequisites.

Appendix A references all the changes made to this document between successive Frama-C releases.

In the index, page numbers written in bold italics (e.g. 1) reference the defining sections for the corresponding entries while other numbers (e.g. 1) are less important references. Furthermore, the name of each OCaml value in the index corresponds to an actual Frama-C

CHAPTER 1. INTRODUCTION

value. In the Frama-C source code, the ocamldoc documentation of such a value contains the special tag Oplugin development guide while, in the html documentation of the Frama-C API, the note "Consult the Plugin Development Guide for additional details" is attached the value name.

The most important paragraphs are displayed inside gray boxes like this one. A plug-in developer **must** follow them very carefully.

There are numerous code snippets in this document. Beware that copy/pasting them from the PDF to your favorite text editor may prevent your code from compiling, because the PDF text can contain non-ASCII characters.

1.2 Outline

This guide is organised in four parts.

- Chapter 2 is a step-by-step tutorial for developing a new plug-in within the Frama-C platform. At the end of this tutorial, a developer should be able to extend Frama-C with a simple analysis available as a Frama-C plug-in.
- Chapter 3 presents the Frama-C software architecture.
- Chapter 4 details how to use all the services provided by Frama-C in order to develop a fully integrated plug-in.
- Chapter 5 is a reference manual with complete documentation for some particular points of the Frama-C platform.

Chapter 2 Tutorial

Target readers: beginners.

This chapter aims at helping a developer to write his first Frama-C plug-in. At the end of the tutorial, any developer should be able to extend Frama-C with a simple analysis available as a Frama-C plug-in. This chapter was written as a step-by-step explanation on how to proceed towards this goal. It will get you started, but it does not tell the whole story. You will get it with your own experiments, and by reading the other chapters of this guide as needed.

First, Section 2.1 describes how to quickly setup a development environment for Frama-C. Section 2.2 shows what a plug-in looks like. Then Section 2.3 explains the basis for writing a standard Frama-C plug-in, while Section 2.4 details how to interact with Frama-C and other plug-ins to implement analyzers of C programs.

2.1 Quick Setup of a Development Environment

This setup is based on Emacs as the IDE, with OPAM for OCaml package installation and Merlin for OCaml source code navigation. Similar environments can be setup using other editors, such as Vim and Sublime Text, but they are not detailed here; please refer to the Merlin documentation for further details on how to setup other editors for OCaml development.

2.1.1 Emacs Configuration Files

The Frama-C source distribution includes, in its share directory, some frama-c-*.el files (*Emacs-lisp* scripts) with default settings for an OCaml development environment based on Emacs + OPAM + Merlin. To set it up, do the following:

- 1. Install Emacs, OPAM, and OPAM packages merlin, tuareg and ocp-indent;
- 2. Copy share/emacs/frama-c-*.el to a directory in your Emacs load-path;
- 3. Add (load-library "frama-c-recommended") to your .emacs init file.

For instance, run these commands (after having installed OPAM):

```
opam install merlin tuareg ocp-indent
mkdir ~/.emacs.d/frama-c
cp <path to frama-c sources>/share/emacs/frama-c-*.el ~/.emacs.d/frama-c/
```

And then add this in the beginning of your ~/.emacs:

```
(add-to-list 'load-path "~/.emacs.d/frama-c")
(load-library "frama-c-recommended")
```

You can replace frama-c-recommended with frama-c-dev in the above line. The former contains some extra, optional settings, while the latter contains only the most important settings for OCaml development. We recommend you review the definitions in frama-c-recommended and remove those you find unnecessary.

2.1.2 Quick Merlin guide

Merlin¹ is a tool for OCaml type information, source code navigation and auto-completion.

Detailed instructions for using Merlin with Emacs are available at https://github.com/ the-lambda-church/merlin/wiki/emacs-from-scratch.

The Frama-C Makefile contains a target merlin that generates an appropriate .merlin file to be used when editing Frama-C .ml/.mli files. Run make merlin after compiling Frama-C, and the generated .merlin file will be automatically used when opening Frama-C OCaml sources.

Here is a quick summary of the most useful commands when editing .ml/.mli files:

- Ctrl+c Ctrl+t: display type information (repeat it to further expand types)
- Ctrl+c Ctrl+l: jump to definition (for variables, types, modules, etc.)
- Ctrl+c Ctrl+x: jump to next error in current buffer

Merlin also includes an auto-complete feature. Check its website for further documentation.

2.2 What Does a Plug-in Look Like?

Figure 2.1 shows how a plug-in can integrate with the Frama-C platform. This tutorial focuses on specific parts of this figure.

The implementation of the plug-in is provided inside a specific directory. The plug-in registers with the Frama-C platform through kernel-provided registration points. These registrations are performed through hooks (by applying a function or a functor). For instance, the next section shows how to:

- extend the Frama-C entry point thanks to the function Db.Main.extend if you want to run plug-in specific code whenever Frama-C is executed;
- use specific plug-in services provided by the module Plugin, such as adding a new Frama-C option.

 $^{^1 \}rm Merlin$ is available on Github (https://github.com/the-lambda-church/merlin) and as an OPAM package.

2.3. THE HELLO PLUG-IN




Figure 2.1: Plug-in Integration Overview.

2.3 The Hello plug-in

This simple plug-in explain how to make your plug-in interact basically with several aspects of the Frama-C framework: registration, getting command-line options, compilation and installation, console output, testing, and documentation. (In case of difficulty, it is explained at the end of this section how to generate the whole plug-in.)

2.3.1 A Simple Script

The easiest way to extend Frama-C is to write a simple script. A simple 'Hello World' script consists of a single OCamI file:

File ./hello_world.ml²

```
let run () =
  try
   let chan = open_out "hello.out" in
   Printf. fprintf chan "Hello, world!\n";
   flush chan;
   close_out chan
  with Sys_error __ as exc →
   let msg = Printexc.to_string exc in
   Printf.eprintf "There was an error: %s\n" msg
let () = Db.Main.extend run
```

This script defines a simple function that writes a message to an output file, then registers the function **run** as an entry point for the script. **Frama-C** will call it among the other plug-in entry points if the script is loaded.

The script is compiled, loaded and run with the command frama-c -load-script hello_world.ml. Executing this command creates a hello.out file in the current directory.

2.3.2 Registering a Script as a Plug-in

To make this script better integrated into Frama-C, its code must register itself as a plug-in. Such a registration provides general services, such as outputting on the Frama-C console, or extending Frama-C with new command-line options.

Registering a plug-in is achieved through the use of the Plugin.Register functor:

```
File ./hello_world.ml
```

```
let help msg = "output a warm welcome message to the user"
module Self = Plugin.Register
  (struct
    let name = "hello world"
    let shortname = "hello"
    let help = help_msg
 end)
|et run () =
  trv
    let chan = open_out "hello.out" in
    Printf.fprintf chan "Hello, world!\n";
    flush chan;
   close\_out chan
 with Sys_error _ as \mathrm{exc} \rightarrow
    let msg = Printexc.to_string exc in
    Printf.eprintf "There was an error: %s\n" msg
let () = Db.Main.extend run
```

The argument for this functor is a module with three values:

- name is an arbitrary, non-empty string containing the full name of the module.
- shortname is a small string containing the short name of the module, usually used as a prefix for plug-in options. No space is allowed in that string.

• help is a string containing free-form text, containing a description of the module.

Visible results of the registration include:

- "hello world" appears in the list of available plug-ins (consultable with frama-c -load-script hello_world.ml -plugins);
- default options for the plug-in work, including the inline help (available with frama-c -load-script hello_world.ml -hello-help).

2.3.3 Displaying Messages

The signature of the module Self obtained by applying Plugin.Register is General_services. One of these general services is logging, *i.e.* message display. In Frama-C, one should never attempt to write messages directly to stderr or stdout: use the general services instead³.

```
File ./hello_world.ml
   let help msg = "output a warm welcome message to the user"
   module Self = Plugin.Register
     (struct
       let name = "hello world"
       let shortname = "hello"
       let help = help_msg
     end)
   let run () =
     Self.result "Hello, world!";
     |et product =
       Self.feedback ~level:2 "Computing the product of 11 and 5...";
       11 * 5
     in
     Self. result "11 * 5 = %d" product
   let () = Db.Main.extend run
```

Running this script yields the following output:

```
$ frama-c -load-script hello_world.ml
[hello] Hello, world!
[hello] 11 * 5 = 55
```

The result routine is the function to use to output results of your plug-in. The Frama-C output routines takes the same arguments than the OCaml function Format.printf.

The function **feedback** outputs messages that show progress to the user. In this example, we gave to feedback a log level of 2, because we estimated that in most case the user is not interested in seeing the progress of a fast operation (simple multiplication). The default log level is 1, so by default this message is not displayed. To see it, the verbosity of the **hello** plug-in must be increased:

³However writing to a new file using standard OCaml primitives is OK.

```
$ frama-c -load-script hello_world.ml -hello-verbose 2
[hello] Hello, world!
[hello] Computing the product of 11 and 5...
[hello] 11 * 5 = 55
```

For a comprehensive list of the logging routines and options, see Section 4.7.

2.3.4 Adding Command Line Options

We now extend the hello world plug-in with new options.

If the plug-in is installed (with make install), it will be loaded and executed on every invocation of frama-c, which is surely not what you want. To avoid this behavior, we add a boolean option, set by default to false, that conditionally enables the execution of the main function of the plug-in (the usual convention for the name of the option is to take the short name of the module with no suffix, *i.e.* -hello in our case).

We also add another option, -hello-output, that takes a string argument. When set, the hello message is displayed in the file given as argument.

```
File ./hello_world.ml
```

```
let help_msg = "output a warm welcome message to the user"
module Self = Plugin.Register
  (struct
    let name = "hello world"
    let shortname = "hello"
    let help = help_msg
 end)
module Enabled = Self.False
  (struct
    let option name = "-hello"
    let help = "when on (off by default), " ^ help_msg
  end)
module Output_file = Self.String
  (struct
    let option_name = "-hello-output"
    let default = "-"
    let arg_name = "output-file"
    |et help =
     "file where the message is output (default: output to the console)"
  end)
let run () =
  trv
  if Enabled.get() then
    let filename = Output_file.get () in
    let output msg =
      if Output_file.is_default() then
       Self.result "%s" msg
      else
        let chan = open out filename in
        Printf. fprintf chan "%s\n" msg;
```

```
flush chan;
close_out chan;
in
output "Hello, world!"
with Sys_error __ as exc →
let msg = Printexc.to_string exc in
Printf.eprintf "There was an error: %s\n" msg
```

```
let () = Db.Main.extend run
```

Registering these new options is done by calling the Self.False and Self.String functors, which respectively creates a new boolean option whose default value is false and a new string option with a user-defined default value (here "-"). The values of these options are obtained *via* Enabled.get () and Output_file.get ().

With this change, the hello message is displayed only if Frama-C is executed with the -hello option.

```
$ frama-c
$ frama-c -load-script hello_world.ml -hello
[hello] Hello, world!
$ frama-c -load-script hello_world.ml -hello -hello-output hello.out
$ ls hello.out
hello.out
```

These new options also appear in the inline help for the hello plug-in:

2.3.5 Writing a Makefile

The use of load-script is ideal for small experimentations, or when writing very specific extensions. When a plug-in becomes larger, or more general-purpose, and must be split into several files, it is a good idea to build and install it properly. Frama-C provides means to simplify this through the use of Makefiles.

First, lets us create a hello directory that will contain all of our plug-in files. We put hello_world.ml inside it, and then create our Makefile there.

A simple Makefile

We write a simple ./Makefile for our ./hello_world.ml plug-in:

File ./Makefile

```
FRAMAC_SHARE := $(shell frama-c-config -print-share-path)
PLUGIN_NAME = Hello
PLUGIN_CMO = hello_world
include $(FRAMAC_SHARE)/Makefile.dynamic
```

This Makefile sets some variables before including the generic Makefile.dynamic which is installed within Frama-C. It may be customized in several ways to help building a plug-in (see Section 4.4 for details).

The name of each compilation unit (here hello_world) must be different from the plug-in name set by the Makefile (here Hello), from any other plug-in names (*e.g.* value^{*a*}) and from any other Frama-C kernel OCaml files (*e.g.* plug-in).

 $^a \texttt{value}$ is the technical plug-in name of the Eva plug-in

The plug-in also needs an interface file. Indeed, thanks to Makefile.dynamic, each plug-in is packed into a single module **\$(PLUGIN_NAME)** (here Hello) which needs an interface. Here we simply export an empty interface in order to hide the whole implementation to other developers.

File ./Hello.mli

(** Hello World plug-in.

No function is exported. *)

Note the unusual capitalization of the filename Hello.mli which is required for compilation purposes.

Inside the plug-in's directory, run make to compile it. Note that the compiled files are copied into a top (for *top-level*) subdirectory (if our plug-in had GUI-dependent modules, they would be placed in a gui subdirectory). The module can then be loaded and executed by using frama-c -load-module top/Hello.

Then run make install to install the plug-in (you need to have write access to the plugins directory, located at the path given by the command frama-c-config -print-libpath).

Just launch frama-c (without any option): the Hello plug-in is now always loaded, without the need to pass other options to the command line. Check it with the command frama-c -hello-help.

Splitting your source files

Here is a slightly more complex example where the plug-in has been split into several files. Usually plug-in registration through Plugin.Register should be done at the bottom of the module hierarchy, while registration of the run function through Db.Main.extend should be at the top, as in the following example. The PLUGIN_CMO variable must contain the list of file names, in the correct OCaml build order.

File ./Makefile

```
FRAMAC_SHARE := $(shell frama-c-config -print-share-path)
PLUGIN_NAME = Hello
PLUGIN_CMO = hello_options hello_print hello_run
include $(FRAMAC_SHARE)/Makefile.dynamic
```

The three following files completely replace the ./hello_world.ml from the previous section. Modules are directly called by their name in the classical OCaml way.

File ./hello_options.ml

2.3. THE HELLO PLUG-IN

```
let help_msg = "output a warm welcome message to the user"
module Self = Plugin.Register
  (struct
    let name = "hello world"
    let shortname = "hello"
    let help = help msg
 end)
module Enabled = Self.False
  (struct
    let option_name = "-hello"
    let help = "when on (off by default), " ^ help_msg
   end)
module Output_file = Self.String
  (struct
    let option name = "-hello-output"
    let default = "-"
    let arg_name = "output-file"
    let help =
     "file where the message is output (default: output to the console)"
  end)
```

File ./hello_print.ml

```
let output msg =
  try
  let filename = Hello_options.Output_file.get () in
  if Hello_options.Output_file.is_default () then
    Hello_options.Self.result "%s" msg
  else
    let chan = open_out filename in
    Printf.fprintf chan "%s\n" msg;
    flush chan;
    close_out chan
with Sys_error _ as exc →
    let msg = Printexc.to_string exc in
    Printf.eprintf "There was an error: %s\n" msg
```

File ./hello_run.ml

```
let run () =
    if Hello_options.Enabled.get() then
        Hello_print.output "Hello, world!"
```

```
let () = Db.Main.extend run
```

The plug-in can be tested again by running:

```
$ make
$ make install
<...>
$ frama-c -hello -hello-output hello.out
$ more hello.out
Hello, world!
```

However, this does not consist in a proper test *per se*. The next section presents how to properly test plug-ins.

2.3.6 Testing your Plug-in

Frama-C supports non-regression testing of plug-ins. This is useful to check that further plug-in modifications do not introduce new bugs. The tool allowing to perform the tests is called **ptests**.

To build these tests, the location of the subdirectories containing them must be indicated in the Makefile through the variable PLUGIN_TESTS_DIRS set at hello as this will be the name of the subdirectory of .tests/ where the plug-in's tests will be located:

File ./Makefile

```
FRAMAC_SHARE := $(shell frama-c-config -print-share-path)
PLUGIN_NAME = Hello
PLUGIN_CMO = hello_options hello_print hello_run
PLUGIN_TESTS_DIRS := hello
include $(FRAMAC_SHARE)/Makefile.dynamic
```

This enables the creation of a ./tests/ptests_config file holding the environement needed by ptests to run the plug-in's tests by running:

\$ mkdir tests
\$ make
<...>
Generating tests/ptests_config

For non-regression testing, the current behaviour of a program is taken as the oracle against which future versions will be tested. In this tutorial, the test will be about the correct Hello, world! output made by the option -hello of the plug-in.

Each test directory must contain a run.config comment with the test directives and the C source code used for the test. (There are other ways to declare and control tests as developed in Section 4.5.2.) For this tutorial, there will be no such source code. A file ./tests/hello/hello_test.c is then created:

```
File ./tests/hello/hello_test.c
    /* run.config
    OPT: -hello
```

*/

In this file, there is only one directive OPT: -hello which requires to run Frama-C on this test with the -hello option. A look at Section 4.5.5 gives you an idea of the kind of directives which can be used to test plug-ins.

Once the **run.config** has been configured, it becomes possible to get the output generated by the plug-in:

```
$ ptests.opt -show
Env:
<...>
Command:
/usr/local/bin/frama-c.byte tests/hello/hello_test.c -check -hello 2>tests/
    hello/result/hello_test.err.log >tests/hello/result/hello_test.res.log
```

2.3. THE HELLO PLUG-IN

```
[kernel] Parsing FRAMAC_SHARE/libc/__fc_builtin_for_normalization.i (no
    preprocessing)
[kernel] Parsing tests/hello/hello_test.c (with preprocessing)
[hello] Hello, world!
Env:
<...>
Command:
<...>
```

The option -show runs the tests and shows the output (but not their examination). Other options are detailed in Section 4.5.4 to give a better idea of the extent to which ptests is configurable. Under Env is displayed the context (coming from the file ./hello/ptests_config). Then, Command shows the executed command for this test case followed by bash pipes to control the dataflow. (Note the -hello option which has been passed to Frama-C as requested by OPT: -hello in the run.config.) Two outputs are considered as results for each test: an *error* output and a *result* output. These outputs are logged in the two following files: ./tests/hello/result/hello_test.err.log and ./tests/hello/result/hello_test.res.log. The three lines beginning by [kernel] and [hello] are the actual non-erroneous outputs made by Frama-C: two of them are generated by the kernel (which could be muted by changing the verbosity) while the third one is generated by our plug-in Hello. Env and Command parts appear once again because some test strategies need it, which is not the case in the simple setting of this tutorial.

Once you have verified the output is as expected, set it as an oracle to be used for later non-regression tests by running:

\$ ptests.opt -update

This command copies the two log files to ./tests/hello/oracle/hello_test.err.oracle and ./tests/hello/oracle/hello_test.res.oracle.

The setting of this test case is now finished. Let's now assume the plug-in is later erroneously modified as follows:

```
File ./hello_run.ml
```

let run () =
 if Hello_options.Enabled.get() then
 Hello_print.output "Hello world!"

let () = Db.Main.extend run

where Hello, world! is incorrectly changed to Hello world!. Running the command:

```
$ make
<...>
$ make tests
TESTING PLUG-IN Hello
% Dispatch finished, waiting for workers to complete
Env:
<...>
Command:
<...>
% Comparisons finished, waiting for diffs to complete
--- tests/hello/oracle/hello_test.res.oracle 2017-06-02 14:39:49.407624816
+0200
```

CHAPTER 2. TUTORIAL

```
+++ tests/hello/result/hello_test.res.log 2017-06-02 14:40:03.483624679
+0200
@@ -1,3 +1,3 @@
[kernel] Parsing FRAMAC_SHARE/libc/__fc_builtin_for_normalization.i (no
    preprocessing)
[kernel] Parsing tests/hello/hello_test.c (with preprocessing)
-[hello] Hello, world!
+[hello] Hello world!
% Diffs finished. Summary:
Run = 1
Ok = 1 of 2
Time = 0.380000 s.
real 0.45
user 0.38
sys 0.03
```

displays the differences (à la diff) between the current executions and the saved oracles. Here the diff clearly shows that the only difference is the missing comma in the generated message due to our (erroneous) modification. One test is marked as being successful: that is the test comparing stderr (which contains an empty string). After fixing the OCaml code, running make && make tests again shows that all test cases are successful.

You may use other Frama-C's plug-ins as examples of how to integrate a plug-in with ptests. Small plug-ins such as Report and Variadic are good examples (see directories src/plugins/report/tests/ and src/plugins/variadic/tests/). Please note Frama-C offers no particular support for other kinds of testing purposes, such as test-driven development $(TDD)^4$ for instance. Additional information about plug-in testing is available in Sections 4.5 and 5.3.

2.3.7 Documenting your Source Code

Frama-C automatically generates the documentation of plug-ins when the command make doc is run^5 . This relies on ocamldoc and requires the plug-in to be documented following the ocamldoc guidelines (please refer to the corresponding chapter in [13]).

We show here how the Hello plug-in could be slightly documented and use **ocamldoc** features such as @-tags and cross references:

```
File ./hello_options.ml
```

```
(** This module contains the possible command line options
  for the Hello plug-in.
  @author Anne Onymous
  @see < http://frama-c.com/download/
      frama-c-plugin-development-guide.pdf>
      Frama-C Developer Manual, Tutorial
*)
(** Content of the welcome message. *)
let help msg = "output a warm welcome message to the user"
```

⁴For the purpose of driving the development of a plug-in, one should have to manually create ./tests/*/oracle/*.err.oracle and ./tests/*/oracle/*.res.oracle files for example.

⁵Frama-C kernel needs to have been installed with code documentation support. If this was not the case, you can run make doc install-doc-code in Frama-C's main directory as hinted by the error message appearing in the terminal before trying again to generate the documentation of the plug-in.

```
(** Registration of the plug-in to Frama-C. *)
module Self = Plugin.Register
  (struct
    let name = "hello world"
   let shortname = "hello"
   let help = help msg
 end)
(** Enabling of the plug-in. *)
module Enabled = Self.False
  (struct
    let option_name = "-hello"
    let help = "when on (off by default), " ^{\rm help} msg
  end)
(** Output of the plug-in. *)
module Output file = Self.String
  (struct
    let option_name = "-hello-output"
   let default = "-"
   let arg_name = "output-file"
   let help =
     "file where the message is output (default: output to the console)"
  end)
```

File ./hello_print.ml

```
(** This module contains the printing method of the Hello plug-in.
   @author Anne Onymous
   @see < http://frama-c.com/download/
           frama-c-plugin-development-guide.pdf>
       Frama-C Developer Manual, Tutorial
*)
(** Outputs a message to the output selected in
       {!module:Hello_options.Output_file}.
   @param msg Message to output.
   @raise Sys_error if filesystem error.
*)
let output msg =
 try
   let filename = Hello_options.Output_file.get () in
    if Hello_options.Output_file.is_default () then
     Hello_options.Self.result "%s" msg
    else
      let chan = open out filename in
      Printf. fprintf chan "%s\n" msg;
     flush chan;
     close_out chan
 with Sys_error _ as exc \rightarrow
    let msg = Printexc.to_string exc in
    Printf.eprintf "There was an error: %s\n" msg
```

```
File ./hello_run.ml
```

CHAPTER 2. TUTORIAL

```
(** This module contains the main control logic of the Hello plug-in.
@author Anne Onymous
@see < http://frama-c.com/download/
frama-c-plugin-development-guide.pdf>
Frama-C Developer Manual, Tutorial
*)
(** Controls the output of a given message by
{!val:Hello_print.output} depending on the state of
{!module:Hello_options.Enabled}.
*)
let run () =
if Hello_options.Enabled.get() then
Hello_print.output "Hello, world!"
(** Definition of the entry point of the hello plug-in. *)
let () = Db.Main.extend run
```

The documentation files of the plug-in are added to ./doc/code/ and the link to this is added to the plug-ins index file ./doc/code/index.html.

This simple tutorial now comes to its end. It focused on the standard features of architectures and interfaces of Frama-C plug-ins. A companion archive hello.tar.gz is available in the download section of the Frama-C website⁶. The next tutorial will make you dive in C analysis.

2.4 The ViewCfg plug-in

In this section, we create a new ViewCfg plug-in that computes the control flow graph of a function and outputs it in the DOT format. Through its implementation, we explain some of Frama-C APIs such as how to visit an AST⁷, to hook a plug-in, to interface a plug-in with other plug-ins, to extend the GUI⁸, to make a plug-in usable by others, to make write a plug-in into the journal, to configure a script, and to make a plug-in usable in a multi-projects setting.

This section assumes the reader is already familiar with the basics of plug-ins for Frama-C as covered by the Hello plug-in in the previous section.

2.4.1 Visiting the AST

Writing an analysis for C programs is the primary purpose of a Frama-C plug-in. That usually requires to visit the AST to compute information for some C constructs. There are two different ways of doing that in Frama-C:

- through a direct recursive descent; or
- by using the Frama-C visitor.

The first case is usually better if you have to compute information for most C constructs, while the latter is better if only few C constructs are interesting or if you have to write a program transformation. Of course, it is also possible to combine both ways to tune it to specific needs.

⁶The direct link is: http://frama-c.com/download.html.

⁷Abstract Syntax Tree

⁸Graphical User Interface

Pretty-printing with direct recursive descent

Frama-C already has a function to pretty-print statements (namely Printer.pp_stmt), but it is not suitable for us, as it will recursively print substatements of compound statements (blocks, if, while, ...) while we only want to pretty print the node representing the current statement: substatements will be represented by other nodes. Thus we will use the following small function:

The Cil_types module contains the definition of the AST of a C program, like constructors Cil_types.Instr, Cil_types.Return, and so on which are of type Cil_types.stmtkind. The Printer module contains functions that prints the different Cil types. The documentation of these module is available on the Frama-C website⁹, or by typing make doc in the Frama-C source distribution.

Creating the graphs with a visitor

In order to create our output, we must make a pass through the whole AST. An easy way to do that is to use Frama-C visitor mechanism. A visitor is a class with one method per type of the AST, whose default behavior is to just call the method corresponding to each of its children. By inheriting from the visitor, and redefining some of the methods, one can perform actions on selected parts of the AST, without the need to traverse the AST explicitly.

class print_cfg out = object
 inherit Visitor.frama_c_inplace

Here we used the so-called "in place" visitor, which should be used for read-only access to the AST. When performing code transformations, a "copy" visitor should be used, that creates a new project (see section 4.17.4).

There are three kinds of nodes where we have something to do. First, at the file level, we create the whole graph structure.

method! vfile _ =
Format.fprintf out "@[< hov 2> digraph cfg {@ ";
Cil.DoChildrenPost (fun f → Format.fprintf out "}@]@."; f)

Cil.DoChildrenPost is one of the possible visitAction, that tells the visitor what to do after the function is executed. With DoChildrenPost func, the func argument is called

⁹From http://frama-c.com/download.html.

CHAPTER 2. TUTORIAL

once the children have been executed: here we close the parenthesis once that all functions have been printed in the file.

Then, for each function, we encapsulate the CFG in a subgraph, and do nothing for the other globals.

Cil.SkipChildren tells the visitor not to visit the children nodes, which makes it more efficient¹⁰.

Last, for each statement, we create a node in the graph, and create the edges toward its successors:

```
method! vstmt_aux s =
Format.fprintf out "@[< hov 2> s%d@ [label=%S]@];@ "
    s.sid (Pretty_utils.to_string print_stmt s.skind);
List.iter
    (fun succ → Format.fprintf out "@[s%d → s%d;@]@ " s.sid succ.sid)
    s.succs;
Format.fprintf out "@]";
Cil.DoChildren
```

This code could be optimized, for instance by replacing the final DoChildren by SkipChildren for statements that cannot contain other statements, like Instr, and avoid visiting the expressions.

Finally we close the object definition:

end

Hooking into Frama-C

It just remains to hook this script into Frama-C.

```
let run () =
    let chan = open_out "cfg.out" in
    let fmt = Format.formatter_of_out_channel chan in
    Visitor.visitFramacFileSameGlobals (new print_cfg fmt) (Ast.get ());
    close_out chan
```

let () = Db.Main.extend run

Assuming the script is called cfg_print.ml, it can then be run with:

```
frama-c -load-script cfg_print.ml [other_options] file.c [file2.c]
```

And the graph can be visualized with

```
dotty cfg.out
```

This produces a graph like in Figure 2.2

¹⁰In a copying visitor, Cil.JustCopy should have been used instead.

2.4. THE VIEWCFG PLUG-IN




Figure 2.2: Control flow graph for file test.c.

Further improvements

There are many possible enhancements to this code:

- There is a bug when trying to print statements that contain strings (such as printf("Hello\n") such statements must be protected using the "%S" Format directive;
- The script could be transformed into a regular plug-in, by registering into Frama-C, and taking options from the command line; for instance to compute the control flow graph of a single function given as an argument;
- The graphs could be fancier, in particular by distinguishing between branching nodes and plain ones, or showing exit of blocks as well as their beginning; or linking a call with the called function.

We will concentrate on another extension, which is to reuse the analysis of the value Frama-C plug-in to color unreachable nodes. To do so, because we will combine different plug-ins, we need to ensure their correct ordering. This requires the definition of some command-line options.

2.4.2 Plug-In registration and command-line options

We have already seen how to register options in the previous "Hello" tutorial. We now apply these principles to the ViewCfg plug-in.

CHAPTER 2. TUTORIAL

```
module Self = Plugin.Register(struct
  let name = "control flow graph"
  let shortname = "viewcfg"
  let help = "control flow graph computation and display"
end)
module Enabled = Self.False(struct
  let option name = "-cfg"
  let help =
   "when on (off by default), computes the CFG of all functions."
end)
module OutputFile = Self.String(struct
  let option_name = "-cfg-output"
  let default = "cfg.dot"
  let arg_name = "output-file"
  let help = "file where the graph is output, in dot format."
end)
|et run () =
  if Enabled.get() then
    let filename = OutputFile.get () in
    let chan = open out filename in
    let fmt = Format.formatter of out channel chan in
    Visitor.visitFramacFileSameGlobals (new print_cfg fmt) (Ast.get ());
   close out chan
```

```
let () = Db.Main.extend run
```

We added two options, -cfg to compute the CFG conditionally (important for ordering plug-in executions), and -cfg-output to choose the output file.

An interesting addition would be a -cfg-target option, which would take a set of files or functions whose CFG would be computed, using the Self.Kernel_function_set functor. Depending on the targets, visiting the AST would have different starting points. This is left as an exercise for the reader.

Another interesting exercise is to solve the following problem. Currently, the complete CFG for the whole application is computed in each Frama-C step, *i.e.* executing frama-c test.c -cfg -then -report would compute the CFG twice. Indeed, the -cfg option sets Enabled to true, and the run function is executed once per task. To solve this problem, one has to create a boolean state to remember that the plug-in has already been executed. The apply_once function in the State_builder module helps dealing with this issue (reading the section 2.4.9 of this tutorial and section 4.11 of this manual should help you understand the underlying notion of states).

With these command-line options, we can properly interface our ViewCfg plug-in with the value plug-in.

2.4.3 Interfacing with a kernel-integrated plug-in

Kernel-integrated plug-ins, such as value, use a special mechanism to statically register their APIs for other plug-ins that wish to access them. This mechanism is the Db module of the Frama-C kernel, the entry point for all kernel-integrated plug-ins. By using the functions

exported through the Db.Value module, our plug-in will obtain reachability information computed by value.

The code modification we propose is to color in pink the nodes guaranteed to be unreachable by the value analysis. For this purpose, we change the **vstmt_aux** method in the visitor:

```
method! vstmt_aux s =
  let color =
    if Db.Value.is_computed () then
        let state = Db.Value.get_stmt_state s in
        let reachable = Db.Value.is_reachable state in
        if reachable then "fillcolor=\"#ccffcc\" style=filled"
        else "fillcolor=pink style=filled"
        else ""
    in
    Format.fprintf out "@[s%d@ [label=%S %s]@];@ "
        s.sid (Pretty_utils.to_string print_stmt s.skind) color;
    List.iter
        (fun succ → Format.fprintf out "@[s%d → s%d;@]@ " s.sid succ.sid)
        s.succs;
    Cil.DoChildren
```

This code fills the nodes with green if the node may be reachable, and in pink if the node is guaranteed not to be reachable; but only if the value analysis was previously computed.

To test this code, frama-c should be launched with:

frama-c test.c -load-script cfg_print.ml -val -then -cfg && dotty cfg.out

Note that the relative order of the parameters -load-script and -val in this example is not relevant (see Section 4.13 for details). However, it is important to ensure that -cfg is separated from -val by a -then; otherwise, it is not guaranteed that the value plug-in will run before the ViewCfg plug-in, which might lead to a non-colored graph in some cases, and colored in others.

The resulting graph is shown in Figure 2.3.

2.4.4 Extending the Frama-C GUI

In this section, we will extend our plug-in so that the control flow graph can be displayed interactively. For that, we will extend the Frama-C GUI so that when you right-click on a function in the code, a new "Show CFG" item appears, that displays the control flow graph of the function in a dialog box. This is achieved just by appending the following pieces of code at the end of the cfg_print.ml file.

Currently, we used a visitor that outputs a DOT file with the CFG of all functions of all files. We use dump_function to output the CFG of a single function instead.

let dump_function fundec fmt =
 Format.fprintf fmt "@[< hov 2> digraph cfg {@ ";
 ignore(Visitor.visitFramacFunction (new print_cfg fmt) fundec);
 Format.fprintf fmt "}@]@\n"

We reused the print_cfg visitor, but we selected a different starting point. The argument fundec gets type Cil_types.fundec, which is the CIL type representing a function definition.

Now we write the GUI extension code:




Figure 2.3: Control flow graph colored with reachability information.

```
let cfg selector
   (popup_factory:GMenu.menu GMenu.factory) main_ui ~button:_ localizable =
 match localizable with
 (* Matches global declarations that are functions. *)
  | Pretty_source.PVDecl(_, _, ({vtype = TFun(_,_,_)} as vi)) \rightarrow
   |et callback () =
     let kf = Globals.Functions.get vi in
     let fundec = Kernel_function.get_definition kf in
     let window:GWindow.window = main_ui#main_window in
     Dgraph_helper.graph_window_through_dot
       ~parent:window ~title:"Control flow graph"
       (dump function fundec)
   in
   ignore (popup_factory#add_item "Show _CFG" ~callback)
  | \rightarrow ()
let main_gui main_ui = main_ui#register_source_selector cfg_selector
let () = Design.register_extension main_gui
```

Let us explain this code from the end. Design.register_extension is the entry point for extending the GUI. Its argument is a function which takes as argument an object corresponding to the main window of the Frama-C GUI. This object provides access to the main widgets of the window, and several extension points.

Here we have implemented a single extension, the "source selector", that allows to add entries to menu obtained when right-clicking on the source. This is implemented by the cfg_selector function.

2.4. THE VIEWCFG PLUG-IN

This function takes a localizable argument, which gives information on where the user clicks on the source. Here we do something only if the user clicks on the declaration of a variable whose type is a function (*i.e.* when the user clicked on a function declaration or definition). In that case, we add an item to the popup menu, that calls the callback function if clicked. The callback function calls a Frama-C GUI function that displays a graph from DOT printing functions. It uses several important Frama-C APIs: Globals and Kernel_function, which contain several functions for manipulating globals and functions.

Note that this GUI extension could also have been done through a script (instead of a plug-in), but it would have been less than ideal. In particular, the GUI OCaml modules are available only when a script is loaded with frama-c-gui, and not when loaded with frama-c. When the user wants to view the CFG from the GUI, outputting the CFG of all functions in cfg.out is useless. A better architectural solution is to split our plug-in in several files, with its own Makefile, to better manage its functionalities.

2.4.5 Splitting files and writing a Makefile

The Frama-C plug-in development environment allows to split GUI-related and non-GUI related modules, so that GUI-related modules are loaded and run only if Frama-C is executed with frama-c-gui. This requires splitting the module into several files. We choose the following architecture:

- cfg_options.ml implements plug-in registration and configuration options;
- cfg_core.ml implements the main functions for computing the CFG;
- cfg_register.ml implements "global" computation of the CFG using the -cfg option, and hooking into the Frama-C main loop;
- cfg_gui.ml implements GUI registration.

Dependencies between the modules¹¹ is presented on Figure 2.4.




Figure 2.4: CFG plug-in architecture

To break recursive dependencies between OCaml modules, it is typical that plug-in registration is done at the bottom of the module hierarchy, while definition of the **run** function is at the

¹¹This graphic is generated in file doc/code/modules.dot after running make doc.

top. The GUI is also at the top of the hierarchy: the Frama-C Makefile requires that normal plug-in modules do not depend on GUI modules. Note that currently, the dependency from Cfg_core and Cfg_gui to Cfg_register is artificial, but in future evolutions the GUI could depend on configuration options.

File Makefile

```
FRAMAC_SHARE := $(shell frama-c-config -print-share-path)
PLUGIN_NAME = ViewCfg
PLUGIN_CMO = cfg_options cfg_core cfg_register
PLUGIN_GUI_CMO = cfg_gui
include $(FRAMAC_SHARE)/Makefile.dynamic
```

In the Makefile, the PLUGIN_CMO variable must contain the list of file names of the ml files, in the correct OCaml build order. Modules in PLUGIN_CMO must not depend on modules in PLUGIN_GUI_CMO.

We also need to add an interface for the whole plug-in: File ViewCfg.mli

```
(** ViewCfg plug—in.
No function is exported. *)
```

Here is the listing for the different modules:

```
File cfg_options.ml
```

```
module Self = Plugin.Register(struct
  let name = "control flow graph"
  let shortname = "viewcfg"
  let help = "control flow graph computation and display"
end)
module Enabled = Self.False(struct
  let option_name = "-cfg"
  let help =
   "when on (off by default), computes the CFG of all functions."
end)
module OutputFile = Self.String(struct
 let option_name = "-cfg-output"
 let default = "cfg.dot"
 let arg_name = "output-file"
  let help = "file where the graph is output, in dot format."
end)
```

File cfg_core.ml

```
module Options = Cfg_options
open Cil_types

let print_stmt out = function
| Instr i → Printer.pp_instr out i
| Return _ → Format.pp_print_string out "< return> "
| Goto _ → Format.pp_print_string out "< goto> "
| Break _ → Format.pp_print_string out "< break> "
| Continue _ → Format.pp_print_string out "< continue> "
```

```
| If (e,_,_) \rightarrow Format.fprintf out "if %a" Printer.pp_exp e
 | Switch(e,_,_) → Format.fprintf out "switch %a" Printer.pp_exp e
 | Loop _ \rightarrow Format.fprintf out "< loop> "
 | Block _ \rightarrow Format.fprintf out "< block> "
 | UnspecifiedSequence \_ \rightarrow Format.fprintf out "< unspecified sequence> "
 | TryFinally _ | TryExcept _ | TryCatch _ \rightarrow Format.fprintf out "< try> "
 | Throw _ \rightarrow Format.fprintf out "< throw> "
class print_cfg out = object
  inherit Visitor.frama_c_inplace
 method! vfile _ =
   Format.fprintf out "@[< hov 2> digraph cfg {@ ";
   Cil.DoChildrenPost (fun f \rightarrow Format.fprintf out "}@]@."; f)
 method! vglob aux g =
   match g with
   | GFun(f,_) \rightarrow
       Format.fprintf out "@[< hov 2> subgraph cluster_%a {@ \
                           @[< hv 2> graph@ [label=\"%a\"];0]@ "
          Printer.pp_varinfo f.svar
          Printer.pp_varinfo f.svar;
       Cil.DoChildrenPost(fun g \rightarrow Format.fprintf out "}@]@ "; g)
   | \_ \rightarrow Cil.SkipChildren
 method! vstmt_aux s =
   let color =
     if Db.Value.is_computed () then
       let state = Db.Value.get stmt state s in
        let reachable = Db.Value.is reachable state in
       if reachable then "fillcolor=\"#ccffcc\" style=filled"
        else "fillcolor=pink style=filled"
     else ""
   in
   Format.fprintf out "@[s%d@ [label=%S %s]@];@ "
     s.sid (Pretty_utils.to_string print_stmt s.skind) color;
   List . iter
     (fun succ \rightarrow Format.fprintf out "@[s%d \rightarrow s%d;@]@ " s.sid succ.sid)
     s.succs;
   Cil.DoChildren
```

end

```
let dump_function fundec fmt =
  Format.fprintf fmt "@[< hov 2> digraph cfg {@ ";
  ignore(Visitor.visitFramacFunction (new print_cfg fmt) fundec);
  Format.fprintf fmt "}@]@\n"
```

File cfg_register.ml

open Cfg_options open Cfg_core

|et run () =

CHAPTER 2. TUTORIAL

if Enabled.get() then
 let filename = OutputFile.get () in
 let chan = open_out filename in
 let fmt = Format.formatter_of_out_channel chan in
 Visitor.visitFramacFileSameGlobals (new print_cfg fmt) (Ast.get ());
 close_out chan

let () = Db.Main.extend run

File cfg_gui.ml

```
open Cil_types
open Cfg core
module Options = Cfg_options
let cfg_selector
    (popup_factory:GMenu.menu GMenu.factory) main_ui ~button:_ localizable =
  match localizable with
  (* Matches global declarations that are functions. *)
  | Pretty_source.PVDecl(_, _, ({vtype = TFun(_,_,_)} as vi)) \rightarrow
    |et callback () =
      let kf = Globals.Functions.get vi in
      let fundec = Kernel_function.get_definition kf in
      let window:GWindow.window = main_ui#main_window in
     Dgraph_helper.graph_window_through_dot
       ~parent:window ~title:"Control flow graph"
        (dump_function fundec)
    in
    ignore (popup factory#add item "Show _CFG" ~callback)
  | \_ \rightarrow ()
let main gui main ui = main ui#register source selector cfg selector
let () = Design.register_extension main_gui
```

2.4.6 Getting your Plug-in Usable by Others

Not written yet: please report as "feature request" on http://bts.frama-c.com if you really need this section.

2.4.7 Writing your Plug-in into the Journal

Not written yet: please report as "feature request" on http://bts.frama-c.com if you really need this section.

2.4.8 Writing a Configure Script

Not written yet: please report as "feature request" on http://bts.frama-c.com if you really need this section.

2.4. THE VIEWCFG PLUG-IN

2.4.9 Getting your plug-in Usable in a Multi Projects Setting

Registering and using state

In this section, we will learn how to register state into Frama-C. A *state* is a piece of information kept by a plug-in. For instance, the value plug-in computes, for each statement, a table associating to each AST's variable a set of values the program may have at runtime: this association table is a state.

State registration provides several features:

- It allows the state to be saved and reloaded with the rest of the session, for instance when using frama-c -save/frama-c -load;
- It helps maintaining consistency between the AST and the results and parameters of the analysis of the different plug-ins.

In this tutorial, we will store the file representing the DOT output of the control flow graph of a function (as needed by dump_function) as a string, by using a hashtable from fundec to string. Storing this string will allow us to memoize [15] our computation: the string is computed the first time the CFG of a function is displayed, while the following requests will reuse the result of the computation. Registering the hashtable as a Frama-C state is *mandatory* to ensure Frama-C consistency: for instance, by using a standard OCaml hashtable, a user that would have loaded several session through the GUI could observe the CFG of function of a previous session instead of the one he wants to observe.

Registering a state is done by a functor application:

```
module Cfg_graph_state = State_builder.Hashtbl
 (Cil_datatype.Fundec.Hashtbl)
 (Datatype.String)
 (struct
    let name = "Data_for_cfg.Cfg_graph_state"
    let dependencies = [ Ast.self; Db.Value.self ]
    let size = 17
    end);;
```

The State_builder module provides several functors that help registering states. State_builder.Hashtbl allows the developer to create a hashtable. It is parameterized by a module describing the hashtable and its key, a module describing the data associated to keys, and other informations.

The Datatype and Cil_datatype modules describe the hashtable and its associated data, and explain for instance how the datatype should be copied, printed, or marshalled to the disk. They are part of the Type library [18], described in Section 4.8. Datatype provides descriptions for standard OCaml types, and Cil_datatype for the CIL types (in the Cil_types module).

The last module argument describes the initial size of the hashtable, a name (mainly used for internal debugging), and a list of *dependencies*. Here we expressed that our hashtable depends on the Ast and the results of the Value plug-in. For instance, whenever the Frama-C kernel updates one of these states, it will automatically reset our hashtable. This ensures consistency of the analysis: if the Ast of a function changes, or the value analysis is executed with a different entry point, this potentially affects the display of the control flow graph, that we must recompute.

Once the module has been declared, it is fairly easy to use it.

CHAPTER 2. TUTORIAL

let dump_to_string fundec =
 Self.feedback "Computing CFG for function %s" (fundec.svar.vorig_name);
 ignore
 (Visitor.visitFramacFunction (new print_cfg Format.str_formatter) fundec);
 Format.flush_str_formatter ()

let dump_to_string_memoized = Cfg_graph_state.memo dump_to_string

let dump_function fundec fmt =
Format.fprintf fmt "@[digraph cfg {%s}@]@\n"
 (dump_to_string_memoized fundec)

dump_function now takes two steps: first the CFG is printed to a string, then the string is printed to the fmt argument. This allows the dump_to_string part to be *memoized*, *i.e.* the results of dump_to_string are saved so that later calls to dump_function with the same fundec argument reuse that result.

If you launch frama-c-gui with the above code, click on functions to view their CFG, and inspect the console, you will observe that the string "Computing CFG for function ..." is displayed only once per function.

One can see the effects of the dependency on the Value plug-in by first launching the value analysis, inspecting the CFG for the f function, then changing the entry point to f in the CFG and re-running the value analysis. The console indicates that the CFG have been recomputed. Indeed the state of the Value plug-in, and of its dependencies, was reset when the entry point was changed.

Another way to observe how Frama-C automatically handles states is to display a CFG, save the session, close and restart Frama-C, and then reload the session: the control flow graph is not recomputed, which means that Frama-C has automatically saved the Cfg_graph_state with the rest of the session. Everything should also work properly when loading several sessions.

Clearing states, selection and projects

There is one caveat though: if the user computes the CFG before running the Value analysis, and then runs Value, he will not see a colored graph (unless he re-launch the Value analysis with different parameters). This is because the state of the CFG is reset when the state of Value is reset, not when it is first computed.

To solve this problem, we will manually reset the Cfg_graph_state if we detect that the Value analysis has been run since the last time we computed the CFG. For that, we have to remember the previous value of Db.Value.is_computed (), *i.e.* to register another state:

```
module Value_is_computed = State_builder.Ref
(Datatype.Bool)
(struct
    let name = "Data_for_cfg.Value_computed"
    let dependencies = []
    let default () = false
    end);;
```

This new state only consists of a reference to a boolean value.

Then we just replace dump_function in the code above by the following.

```
let dump_function fundec fmt =
    if not (Value_is_computed.get ()) && Db.Value.is_computed () then begin
        Value_is_computed.set true;
        let selection = State_selection.with_dependencies Cfg_graph_state.self in
        Project.clear ~ selection ();
end;
Format.fprintf fmt "@[digraph cfg {%s}@]@." (dump to string memoized fundec)
```

The only part that need to be explained is the notion of *selection* and *project*. A selection is just a set of states; here we selected the state Cfg_graph_state with all its dependencies, as resetting this state would also impact states that would depend on it (even if there is none for now). We use Project.clear to reset the selection.

Project explanation

A project [17] is a consistent version of all the states of Frama-C. Frama-C is multi-AST, *i.e.*Frama-C plug-ins can change the AST of the program, or perform incompatible analysis (*e.g.* with different entry points). Projects consistently groups a version of the AST of the program, with the states related to this AST.

The Project.clear function has type :

```
| val clear: ?selection:State_selection.t \rightarrow ?project:t \rightarrow unit \rightarrow unit
```

The arguments selection and project can be seen as a coordinate system, and the function allows to clear specific versions of specific states. By default, Frama-C functions act on the *current* project. The developer has to use Project.on or optional arguments to act on different projects. Frama-C automatically handles duplication and switch of states when duplicating or changing of projects. This is the last benefit of state registration.

To summarize:

- To store results, plug-ins should register *states*;
- A *project* is a consistent version of all the states in Frama-C, together with a version of the AST;
- A session is a set of projects;
- Frama-C transparently handles the versioning of states when changing or duplicating projects, saving and reloading sessions from disk, etc.
- The version of the state in a project can change; by default Frama-C functions operate on the current project.
- A *selection* is a set of states. *Dependencies* allow to create selections.
- As a plug-in developer, you have to remember that is up to you to preserve consistency between your states and their dependencies by clearing the latter when the former is modified in an incompatible way. For instance, it would have been incorrect to not call **State_selection.with_dependencies** in the last code snippet of this tutorial.

Projects are generally created using copy visitors. We encourage the reader to experiment with multiple projects development by using them. An interesting exercise would be to change the AST so that execution of each instruction is logged to a file, and then re-read that file to print in the CFG how much time each instruction has been executed. Another interesting exercise would be to use the apply_once function so that the ViewCfg plug-in is executed only once, as explained in section 2.4.2 of this tutorial.

Chapter 3 Software Architecture

Target readers: beginners.

In this chapter, we present the software architecture of Frama-C. First, Section 3.1 presents its general overview. Then, we focus on four different parts:

- Section 3.2 explains what a plug-in really is and the main mechanisms of plug-in integration.
- Section 3.3 introduces the libraries that Frama-C provides.
- Section 3.4 introduces the kernel services that plug-in developers might want to use.
- Section 3.5 introduces the kernel internals. You can safely skip it if you are not a Frama-C kernel developer.


3.1 General Description

From a plug-in developer point of view, the main goals of the Frama-C platform is to provide services to ease:

- analysis and source-to-source transformation of big-size C programs;
- addition of new plug-ins; and
- plug-ins collaboration.

In order to reach these goals, Frama-C has a plug-ins based software architecture based on a *kernel*. Historically the *kernel* was itself based on Cil [16]: even if they have evolved separately since the Frama-C Hydrogen age, there are still a lot of similarities between Cil and several modules of the Frama-C kernel (*e.g.* the ASTs).

The Frama-C architecture design is presented in this chapter, and summarized in Figure 3.1. In this figure, each of the four rounded colored boxes represents a subdirectory d of directory src, while each of the small square boxes represents a subdirectory in one subdirectory src/d. The remaining sections will explain the goal of each of these boxes. They do not detail each module of each directory: use the API documentation generated by make doc for that purpose.






Figure 3.1: Frama-C Architecture Design.

3.2 Plug-ins

In Frama-C, plug-ins are program analysis or source-to-source transformations. The ones provided within Frama-C are in directory $src/plugins/plugin_name$. Each plug-in is an extension point of Frama-C which has to be registered through Plugin.Register (see Section 4.6). Frama-C allows plug-in collaborations: a plug-in p can use a list of plug-ins p_1, \ldots, p_n and conversely. Mutual dependences between plug-ins are even possible. If a plug-in is designed to be used by another plug-in, it has to register its API either by providing a .mli file, or through modules Dynamic or Db. The first method is the preferred one, the second one (through module Dynamic) is the only possible one to define mutually dependent plug-ins while the third one (through module Db) is now fully deprecated even if most of the older Frama-C plug-ins are still defined this way.

3.3 Libraries

Libraries are defined in the directory src/libraries. They are either third-party libraries or dedicated independent libraries which may be used by other parts of Frama-C.

Extension of the OCaml standard library are provided in directory src/libraries/stdlib. For instance, modules FCmodule_name (e.g. FCHashtbl) provides a module_name-like interface (e.g. Hashtbl) with an uniform API for all OCaml versions supported by Frama-C and possibly additional useful operations for the corresponding datastructures.

Single-file libraries are provided in directory src/libraries/utils. For instance, Pretty_utils provides pretty-printing facilities.

datatype (directory src/libraries/datatype) and *project* (directory src/libraries/project) are two multiple-files libraries. They are respectively presented in Sections 4.8 and 4.11.

3.4 Kernel Services

The kernel services is defined in directory **src/kernel_services**. It is the part of the Frama-C kernel which may be useful to develop plug-ins.

This services may be split in four main parts:

- two ASTs and the data structures directly built upon them;
- plug-in interactions toolbox;
- predefined generic analyzers;
- the abstract interpretation framework.

The standard AST used by most analyzers is defined in module Cil_types of directory src/kernel_services/ast_data. It contains the types which describes both the C constructs and the ACSL ones [1]. The same directory also contains modules defining datastructures directly based upon the AST (module Globals), functions (module Kernel_function), annotations (module Annotations) and so on. A related directory is src/kernel_services/ast_queries. It contains modules which provides specific operations
in order to get information about AST-related values.

In the same way, an untyped AST quite close of the C input source is defined in module Cabs of directory src/kernel_services/parsetree. This AST is only well suited for syntactic analyzers/program transformers.

Frama-C also provides services to plug-ins which help both their integration in the platform and their interactions with the kernel and the other plug-ins. They enforce some platform-wide consistency by ensuring that some common actions (*e.g.* printing messages to end-users) are handled by all plugins in a similar way. Directory src/kernel_services/cmdline_parameters provides modules which eases the definition of analyzers' parameters accessible by the end-user through command-line options. Similarly, directory src/kernel_services/plugin_entry_points provides modules to interact with the Frama-C kernel or other plug-ins.

Next, Frama-C provides predefined ways to visit the ASTs, in particular through object-oriented visitors defined in directory src/kernel_services/visitors (see Section 4.17). Some predefined analyzers, such as a multiple generic dataflow analysis are provided in directory src/kernel_services/analysis, while some predefined program transformation, such as cloning a function, are provided in directory src/kernel_services/ast_transformations. Finally, Frama-C provides an abstract interpretation toolbox with various lattices in directory abstract_interp.

3.5 Kernel Internals

Target readers: kernel developers.

The kernel internals is defined in directory src/kernel_internals. It is part of the Frama-C kernel which should be useless to develop analysis plug-ins, except possibly for very low-level interactions, or to extend the C or ACSL services of Frama-C. Consequently, if you are not a kernel developer, you can safely ignore this section.

The internals is split in three different parts, each of them being an independent subdirectory:

- the directory src/kernel_internals/parsing contains the lexer and parser which generate the untyped AST (*aka* Cabs) from the C input source code;
- the directory src/kernel_internals/typing contains the compiler which generates the standard AST (*aka* Cil) from the untyped one;
- the directory **src/kernel_internals/runtime** contains modules whose primary purpose is to perform side-effects while Frama-C is booting.

Chapter 4

Advanced Plug-in Development

This chapter details how to use services provided by Frama-C in order to be fully operational with the development of plug-ins. Each section describes technical points a developer should be aware of. Otherwise, one could find oneself in one or more of the following situations ¹ (from bad to worse):

- 1. reinventing the (Frama-C) wheel;
- being unable to do some specific things (e.g. saving results of an analysis on disk, see Section 4.11.2);
- 3. introducing bugs in his/her code;
- 4. introducing bugs in other plug-ins using his/her code;
- 5. breaking the kernel consistency and so potentially breaking all Frama-C plug-ins (*e.g.* if s/he modifies the AST without changing project, see Section 4.11.5).

In this chapter, we suppose that the reader is able to write a minimal plug-in like hello described in chapter 2 and knows about the software architecture of Frama-C (chapter 3). Moreover plug-in development requires the use of advanced features of OCaml (module system, classes and objects, *etc*). Static plug-in development requires some knowledge of autoconf and make. Each section summarizes its own prerequisites at its beginning (if any).

Note that the following subsections can be read in no particular order: their contents are indeed quite independent from one another even if there are references from one chapter to another one. Pointers to reference manuals (Chapter 5) are also provided for readers who want full details about specific parts.

4.1 Frama-C Configure.in

Target readers: not for standard plug-ins developers.

Prerequisite: Knowledge of autoconf and shell programming.

 $^{^{1}}$ It is fortunately quite difficult (but not impossible) to fall into the worst situation by mistake if you are not a kernel developer.

In this Section, we detail how to modify the file configure.in in order to configure plug-ins (Frama-C configuration has been introduced in Section 2.4.8 and 2.4.5).

First Section 4.1.1 introduces the general principle and organisation of configure.in. Then Section 4.1.2 explains how to configure a new simple plug-in without any dependency. Next we show how to exhibit dependencies with external libraries and tools (Section 4.1.4) and with other plug-ins (Section 4.1.5). Finally Section 4.1.3 presents the configuration of external libraries and tools needed by a new plug-in but not used anywhere else in Frama-C.

4.1.1 Principle

When you execute autoconf, file configure.in is used to generate the configure script. Each Frama-C user executes this script to check his/her system and determine the most appropriate configuration: at the end of this configuration (if successful), the script summarizes the status of each plug-in, which can be:

- *available* (everything is fine with this plug-in);
- *partially available*: either an optional dependency of the plug-in is not fully available, or a mandatory dependency of the plug-in is only partially available; or
- *not available*: either the plug-in itself is not provided by default, or a mandatory dependency of the plug-in is not available.

The important notion in the above definitions is *dependency*. A dependency of a plug-in p is either an external library/tool or another Frama-C plug-in. It is either *mandatory* or *optional*. A mandatory dependency must be present in order to build p, whereas an optional dependency provides features to p that are additional but not highly required (especially p must be compilable without any optional dependency).

Hence, for the plug-in developer, the main role of configure.in is to define the optional and mandatory dependencies of each plug-in. Another standard job of configure.in is the addition of options --enable-p and --disable-p to configure for a plug-in p. These options respectively forces p to be available and disables p (its status is automatically "not available").

Indeed configure.in is organised in different sections specialized in different configuration checks. Each of them begins with a title delimited by comments and it is highlighted when configure is executed. These sections are described in Section 5.1. Now we focus on the modifications to perform in order to integrate a new plug-in in Frama-C.

4.1.2 Addition of a Simple Plug-in

In order to add a new plug-in, you have to add a new subsection for the new plug-in to Section *Plug-in wished*. This action is usually very easy to perform by copying/pasting from another existing plug-in (*e.g.* occurrence) and by replacing the plug-in name (here occurrence) by the new plug-in name in the pasted part. In these sections, plug-ins are sorted according to a lexicographic ordering.

For instance, Section *Wished Plug-in* introduces a new sub-section for the plug-in occurrence in the following way.

4.1. FRAMA-C CONFIGURE.IN

- The first argument is the plug-in name,
- the second one is the name of directory containing the source files of the plug-in (usually a sub-directory of src/plugins),
- the third one is an help message for the -enable-occurrence option of configure,
- the last one indicates if the plug-in is enabled by default (yes/no).

The plug-in name must contain only alphanumeric characters and underscores. It must be the same as the name value given as argument to the functor Plugin.Register of section 4.6 (with spaces replaced by underscore). It must also be the same (modulo upper/lower case) as the PLUGIN_NAME variable given in the plugin's Makefile presented in section 4.4.

The macro check_plugin sets the following variables: FORCE_OCCURRENCE, REQUIRE_OCCURRENCE, USE_OCCURRENCE, and ENABLE_OCCURRENCE.

The first variable indicates if the user explicitly requires the availability of occurrence via setting the option --enable-occurrence. The second and third variables are used by others plug-ins in order to handle their dependencies (see Section 4.1.5). The fourth variable ENABLE_OCCURRENCE indicates the plug-in status (available, partially available or not available). If --enable-occurrence is set, then ENABLE_OCCURRENCE is yes (plug-in available); if --disable-occurrence is set, then its value is no (plug-in not available). If no option is specified on the command line of configure, its value is set to the default one (according to the value of the fourth argument of check_plugin).

4.1.3 Configuration of New Libraries or Tools

Some plug-ins need additional tools or libraries to be fully functional. The configure script takes care of these in two steps. First, it checks that an appropriate version of each external dependency exists on the system. Second, it verifies for each plug-in that its dependencies are met. Section 4.1.4 explains how to make a plug-in depend on a given library (or tool). The present section deals with the first part, that is how to check for a given library or tool on a system. Configuration of new libraries and configuration of new tools are similar. In this section, we therefore choose to focus on the configuration of new libraries. This is done by calling a predefined macro called configure_library², or its more specialized version configure_pkg.

configure_pkg is meant to be used for checking the presence of OCaml libraries that are managed as findlib³ packages, which is the case for most modern OCaml libraries nowadays. It takes two arguments, the name of the package (as known by findlib), and a message that will be displayed if the package is not found.

²For tools, there is a macro configure_tool which works in the same way as configure_library. ³http://projects.camlcity.org/projects/findlib.html

The configure_library macro takes three arguments. The first one is the name of the library, the second one is a filename which is used by the script to check the availability of the library. In case there are multiple locations possible for the library, this argument can be a list of filenames. In this case, the argument must be properly quoted (*i.e.* enclosed in a [,] pair). Each name is checked in turn. The first one which corresponds to an existing file is selected. If no name in the list corresponds to an existing file, the library is considered to be unavailable. The last argument is a warning message to display if a configuration problem appears (usually because the library does not exist). Using these arguments, the script checks the availability of the library.

Results of these macros are available through variables which are substituted in the files generated by configure, where *library* stands for the *uppercased* version of the library name.

- For configure_pkg:
 - HAS_OCAML_library is set to yes or no depending on the availability of the library
- For configure_library:
 - HAS_library is set to yes or no depending on the availability of the library
 - SELECTED_library contains the name of the version selected as described above.

If checking for OCaml libraries and object files without configure_pkg, remember that they come in two flavors: bytecode and native code, which have distinct suffixes. Therefore, you should use the variables LIB_SUFFIX (for libraries) and OBJ_SUFFIX (for object files) to check the presence of a given file. These variables are initialized at the beginning of the configure script depending on the availability of a native-code compiler on the current installation.

Example 4.1 The library Lablgtksourceview2 (used to have a better rendering of C sources in the GUI) is part of Lablgtk2 [10]. This is checked through the following command, where LABLGTKPATH_FOR_CONFIGURE is the path where configure has found Lablgtk2 itself.

```
configure_library(
  [GTKSOURCEVIEW],
  [$LABLGTKPATH_FOR_CONFIGURE/lablgtksourceview2.$LIB_SUFFIX],
  [lablgtksourceview not found])
```

4.1.4 Addition of Library/Tool Dependencies

Dependencies upon OCaml packages (checked by configure_pkg) are governed by two macros:

- plugin_require_pkg(*plugin*, *library*) indicates that *plugin* requires *library* in order to be compiled.
- plugin_use_pkg(*plugin*, *library*) indicates that *plugin* uses *library*, but can nevertheless be compiled if *library* is not installed (potentially offering reduced functionality).

Dependencies upon external tools and libraries (checked by configure_library or configure_tool) are governed by two macros:

- plugin_require_external(*plugin*, *library*) indicates that *plugin* requires *library* in order to be compiled.
- plugin_use_external(*plugin*, *library*) indicates that *plugin* uses *library*, but can nevertheless be compiled if *library* is not installed (potentially offering reduced functionality).

Recommendation 4.1 The best place to perform such extensions is just after the addition of p which sets the value of ENABLE_p.

Example 4.2 Plug-in gui requires Lablgtk2 and GnomeCanvas. It also optionally uses DOT for displaying graphs (graph cannot be displayed without this tool). So, just after its declaration, there are the following lines in configure.in.

plugin_require_external(gui,lablgtk)
plugin_require_external(gui,gnomecanvas)
plugin_use_external(gui,dot)

4.1.5 Addition of Plug-in Dependencies

Adding a dependency with another plug-in is quite the same as adding a dependency with an external library or tool (see Section 4.1.4). For this purpose, configure.in uses two macros

- plugin_require(plugin1, plugin2) states that plugin1 needs plugin2.
- plugin_use(plugin1, plugin2) states that plugin1 can be used in absence of plugin2, but requires plugin2 for full functionality.

There can be mutual dependencies between plug-ins. This is for instance the case for plug-ins value and from.

4.2 Plug-in Specific Configure.ac

Target readers: standard plug-ins developers.

Prerequisite: *Knowledge of* autoconf *and shell programming.*

External plug-ins can have their own configuration file, and can rely on the macros defined for Frama-C. In addition, as mentioned in section 4.4.2, those plug-ins can be compiled directly from Frama-C's own Makefile. In order for them to integrate well in this setting, they should follow a particular layout, described below. First, they need to be able to refer to the auxiliary configure.ac file defining Frama-C-specific macros when they are used as stand-alone plug-ins. This can be done by the following code

CHAPTER 4. ADVANCED PLUG-IN DEVELOPMENT

plugin_file is the file which must be present to ensure that autoconf is called in the appropriate directory (see documentation for the AC_INIT macro of autoconf). configure.ac can be found in two ways: either by relying on the FRAMAC_SHARE shell variable (when Frama-C is not installed, *i.e.* when configuring the plug-in together with the main Frama-C), or by calling an installed Frama-C (when installing the plug-in separately). The inclusion of configure.ac needs to be guarded to prevent multiple inclusions, as the configuration file of the plug-in might itself be included by configure.in (see section 4.4.2 for more details).

The configuration of the plug-in itself or related libraries and tools can then proceed as described in Sections 4.1.2 and 4.1.3. References to specific files in the plug-in source directory should be guarded with the following macro:

PLUGIN_RELATIVE_PATH(file)

If the external plug-in has some dependencies as described in sections 4.1.4 and 4.1.5, the configure script **configure** must check that all dependencies are met. This is done with the following macro:

check_plugin_dependencies

It is only after this point that the variables HAS_library, SELECTED_library, and ENABLE_plugin get their final value. If parts of the configure script depends on these variables, they should appear after the call to check_plugin_dependencies.

An external plug-in can have dependencies upon previously installed plug-ins. However two separately installed plug-ins can not be mutually dependent on each other. Nevertheless, they can be compiled together with the main Frama-C sources using the --enable-external option of configure (see section 4.4.2 for more details).

Finally, the configuration must end with the following command:

write_plugin_config(files)

where files are the files that must be processed by configure (as in AC_CONFIG_FILES macro). PLUGIN_RELATIVE_PATH is unneeded here.

For technical reasons, the macros configure_library, configure_tool, check_plugin_dependencies, and write_plugin_config must not be inside a conditional part of the configure script. More precisely, they are using the diversion mechanism of autoconf in order to ensure that the tests are performed after all dependencies information has been gathered from all existing plugins. Diversion is a very primitive, text-to-text transformation. Using those macros within a conditional (or anything that alters the control-flow of the script) is likely to result in putting some unrelated part of the script in the same branch of the conditional.

4.3 Frama-C Makefile

Target readers: not for standard plug-in developers.

Prerequisite: Knowledge of make.

In this section, we detail the use of Makefile dedicated to Frama-C compilation. This file is split in several sections which are described in Section 5.2.2. By default, executing make only displays an overview of commands. For example, here is the output of the compilation of source file src/kernel_services/plugin_entry_points/db.cmo.

\$ make src/kernel_services/plugin_entry_points/db.cmo
Ocamlc src/kernel_services/plugin_entry_points/db.cmo

If you wish the exact command line, you have to set variable VERBOSEMAKE to yes like below.

\$ make VERBOSEMAKE=yes src/kernel_services/plugin_entry_points/db.cmo

4.4 Plug-in Specific Makefile

Prerequisite: *Knowledge of* make.

4.4.1 Using Makefile.dynamic

In this section, we detail how to write a Makefile for a given plug-in. Even if it is still possible to write such a Makefile from scratch, Frama-C provides a generic Makefile, called Makefile.dynamic, which helps the plug-in developer in this task. This file is installed in the Frama-C share directory. So for writing your plug-in specific Makefile, you have to:

- 1. set some variables for customizing your plug-in;
- 2. include Makefile.dynamic.

Example 4.3 A minimal Makefile is shown below. That is the Makefile of the plug-in Hello World presented in the tutorial (see Section 2.3). Each variable set in this example has to be set by any plug-in.

FRAMAC_SHARE := \$(shell frama-c-config -print-share-path)
PLUGIN_NAME = Hello
PLUGIN_CMO = hello_options hello_print hello_run
include \$(FRAMAC_SHARE)/Makefile.dynamic

FRAMAC_SHARE must be set to the Frama-C share directory. PLUGIN_NAME is the capitalized name of your plug-in while PLUGIN_CMO is the list of the files .cmo generated from your OCaml sources. Note that, by default, during compilation of your plug-in all warnings are disabled; it is recommended to define environment variable DEVELOPMENT=yes to enable the standard set of compilation warnings.

To run your specific Makefile, you must have properly installed Frama-C before, or compile your plugin together with Frama-C, as described in section 4.4.2.

You may possibly need to do make depend before running make.

Which variable can be set and how they are useful is explained Section 5.2.3. Furthermore, Section 5.2.5 explains the specific features of Makefile.dynamic.

4.4.2 Compiling Frama-C and external plug-ins at the same time

Target readers: plug-in developers using the git repository of Frama-C.

It is also possible to get a completely independent plug-in recompiled and tested together with Frama-C's kernel. For that, Frama-C must be aware of the existence of the plug-in. This can be done in two ways:

- All sub-directories of src/plugins directory in Frama-C sources which are not known to Frama-C's kernel are assumed to be external plug-ins.
- One can use the --enable-external option of configure which takes as argument the path to the plug-in

In the first case, the plug-in behaves as any other built-in plug-in: autoconf run in Frama-C's main directory will take care of it and it can be enabled or disabled in the same way as the others. If the plug-in has its own configure.in or configure.ac file, the configuration instructions contained in it (in particular additional dependencies) will be read as well.

In the second case, the plug-in is added to the list of external plug-ins at configure time. If the plug-in has its own configure, it is run as well.

Provided it properly uses the variables set by Makefile.dynamic, the plug-in's Makefile does not require specific adaptations depending on whether it is compiled together with the kernel or with respect to an already-existing Frama-C installation. It is however possible to check the compilation mode with the FRAMAC_INTERNAL variable, which is set to yes when compiling together with Frama-C kernel and to no otherwise.

In addition, if a plug-in wishes to install custom files through the install:: target, this target must depend on clean-install. Indeed, Frama-C's main Makefile needs to remove all existing files before performing a fresh installation, in order to avoid potential interference with an obsolete (and usually incompatible) module from a previous installation. Adding the dependency thus ensures that the removal will take place before any new file has been installed.

Example 4.4 If a plug-in wants to install external/my_lib.cm* in addition to the normal plugin files, it should use the following code: ⁴

```
install:: clean-install
    $(PRINT_INSTALL) "My beautiful library"
    $(MKDIR) $(FRAMAC_LIBDIR)
    $(CP) external/my_lib.cm* $(FRAMAC_LIBDIR)
```

4.5 Testing

In this section, we present **ptests**, a tool provided by **Frama-C** in order to perform non-regression and unit tests.

ptests runs the Frama-C toplevel on each specified test (which are usually C files). Specific directives can be used for each test. Each result of the execution is compared from the

 $^{^4}$ Note that the variable FRAMAC_LIBDIR is automatically set in the Frama-C Makefile to the value provided by the command frama-c-config -print-libpath.

previously saved result (called the *oracle*). A test is successful if and only if there is no difference. Actually the number of results is twice that the number of tests because standard and error outputs are compared separately.

First Section 4.5.1 shows how to use ptests. Next Section 4.5.2 introduces how to use predefined directives to configure tests, while Section 4.5.3 explains how to set up various testing goals for the same test base. Last Section 4.5.4 details ptests' options, while Section 4.5.5 describes ptests' directive.

4.5.1 Using ptests

If you're using a Makefile written following the principles given in section 4.4, the simplest way of using ptests is through make tests which is roughly equivalent to

\$ time ./bin/ptests.opt

or

\$ time ptests.opt

depending on whether you're inside Frama-C's sources or compiling a plug-in against an already installed Frama-C distribution.

A specific target \$(PLUGIN_NAME)_TESTS will specifically run the tests of the plugin. One can add new tests as dependencies of this target. The default tests are run by the target \$(PLUGIN_NAME)_DEFAULT_TESTS.

Additionally, when running make tests or make \$(PLUGIN_NAME)_TESTS it is possible to pass options to ptests.opt through the PTESTS_OPTS variable.

Example 4.5 The following command will update the oracles of all tests of the Aoraï plug-in: \$\\$ make PTESTS OPTS=-update Aorai TESTS

ptests.opt runs tests belonging to a sub-directory of directory tests that is specified in ptests configuration file. This configuration file, tests/ptests_config, is automatically generated by Frama-C's Makefile from the options you set in your plugin's Makefile. ptests also accepts specific *test suites* in arguments. A test suite is either the name of a sub-directory in directory tests or a filename (with its path relative to the current directory).

Example 4.6 If you want to test plug-in sparecode and specific test tests/pdg/variadic.c, just run

\$./bin/ptests.opt sparecode tests/pdg/variadic.c

which should display (if there are 7 tests in directory tests/sparecode)

% Dispatch finished, waiting for workers to complete % Comparisons finished, waiting for diffs to complete % Diffs finished. Summary: Run = 8 Ok = 16 of 16

ptests accepts different options which are used to customize test sequences. These options are detailed in Section 4.5.4.

Example 4.7 If the code of plug-in plugin has changed, a typical sequence of tests is the following one.

- \$./bin/ptests.opt plugin
- \$./bin/ptests.opt -update plugin
- \$ make tests

So we first run the tests suite corresponding to **plugin** in order to display what tests have been modified by the changes. After checking the displayed differences, we validate the changes by updating the oracles. Finally we run all the test suites in order to ensure that the changes do not break anything else in Frama-C.

Example 4.8 For adding a new test, the typical sequence of command is the following.

- \$./bin/ptests.opt -show tests/plugin/new_test.c
- \$./bin/ptests.opt -update tests/plugin/new_test.c
- \$ make tests

We first ask ptests to print the output of the test on the command line, check that it corresponds to what we expect, and then take it as the initial oracle. If some changes have been made to the code in order to let **new_test.c** pass, we must of course launch the whole test suite and check that all existing tests are alright.

If you're creating a whole new test suite suite, don't forget to create the sub-directories suite/result and suite/oracle where ptests will store the current results and the oracles for all the tests in suite

4.5.2 Configuration

In order to exactly perform the test that you wish, some directives can be set in three different places. We indicate first these places and next the possible directives.

The places are:

- inside file tests/test_config;
- inside file tests/subdir/test_config (for each sub-directory subdir of tests); or
- inside each test file, in a special comment of the form

```
/* run.config
    ... directives ...
*/
```

In each of the above case, the configuration is done by a list of directives. Each directive has to be on one line and to have the form

```
CONFIG_OPTION:value
```

There is exactly one directive by line. The different directives (*i.e.* possibilities for $CONFIG_OPTION$) are detailed in Section 4.5.5.

Concurrency issues: tests using compiled modules (-load-script or -load-module) may lead to concurrency issues when the same module is used in different test files, or in different test cases within the same file. One way to avoid issues is to serialize tests via MODULE directives, which will take care of the compilation and of adding the corresponding -load-module option to further OPT and STDOPT directives:

```
MODULE: script.cmx
STDOPT: +"-opt1" ...
STDOPT: #"-opt2" ...
```

The .cmx extension is optional and the prefix @PTEST_DIR@/ is automatically added to the module names (the directive accepts a list of modules that can be separed by blank or comma).

In addition, if the same script tests/suite/script.ml is shared by several test files in tests/suite, it is necessary to compile the script once when entering the directory hosting the suite. The MODULE directive is not well suited for that, and it is thus needed to resort to an EXECNOW directive in tests/suite/test_config:

EXECNOW: make -s @PTEST_DIR@/common_module.cmxs

It is then necessary to explicitly use -load-module @PTEST_DIR@/common_module.cmxs in the appropriate OPT and STDOPT directives.

Example 4.9 Test tests/sparecode/calls.c declares the following directives.

```
/* run.config
    OPT: -sparecode-analysis
    OPT: -slicing-level 2 -slice-return main -slice-print
*/
```

These directives state that we want to test sparecode and slicing analyses on this file. Thus running the following instruction executes two test cases.

\$./bin/ptests.opt tests/sparecode/calls.c
% Dispatch finished, waiting for workers to complete
% Comparisons finished, waiting for diffs to complete
% Diffs finished. Summary:
Run = 2
Ok = 4 of 4

4.5.3 Alternative Testing

You may want to set up different testing goals for the same test base. Common cases include:

- checking the result of an analysis with or without an option;
- checking a preliminary result of an analysis, in particular if the complete analysis is costly;
- checking separately different results of an analysis.

This is possible with option -config of ptests, which takes as argument the name of a special test configuration, as in

\$./bin/ptests.opt -config <special_name> plugin

Then, the directives for this test can be found:

- inside file tests/test_config_<special_name>;
- inside file tests/subdir/test_config_<special_name> (for each sub-directory subdir of tests); or
- inside each test file, in a special comment of the form

```
/* run.config_< special_name>
    ... directives ...
*/
```

Multiple configurations may share the same set of directives:

```
/* run.config, run.config_< special_name> [, ...]
    ... common directives ...
*/
```

The following wildcard is also supported, and accepts any configuration: $/\ast$ run.config* .

All operations for this test configuration should take option -config in argument, as in

\$./bin/ptests.opt -update -config <special_name> plugin

In addition, option -config <special_name> requires subdirectories result_<special_name> and oracle_<special_name> to store results and oracle of the specific configuration.

4.5.4 Detailed options

Figure 4.1 details the options of ptests.

The commands provided through the -diff and -cmp options play two related but distinct roles. cmp is always used for each test (in fact it is used twice: one for the standard output and one for the error output). Only its exit code is taken into account by ptests and the output of cmp is discarded. An exit code of 1 means that the two files have differences. The two files will then be analyzed by diff, whose role is to show the differences between the files. An exit code of 0 means that the two files are identical. Thus, they won't be processed by diff. An exit code of 2 indicates an error during the comparison (for instance because the corresponding oracle does not exist). Any other exit code results in a fatal error. It is possible to use the same command for both cmp and diff with the -use-diff-as-cmp option, which will take as cmp command the command used for diff.

The **-exclude** option can take as argument a whole suite or an individual test. It can be used with any behavior.

The -gui option will launch Frama-C's GUI instead of the console-based toplevel. It can be combined with -byte to launch the bytecode GUI. In this mode the default level of parallelism is reduced to 1.

4.5. TESTING

kind	Name	Specification	Default
	-add-options	Additional options appended to the	
Toplevel		normal toplevel command-line	
	-add-options-pre	Additional options prepended to the	
		normal toplevel command line	
	-byte	Use bytecode toplevel	no
	-opt	Use native toplevel	yes
	-gui	Use GUI instead of console-based	no
		toplevel	
	-run	Delete current results; run tests and	yes
		examine results	
Behavior	-dry-run	Print commands, but do not execute	no
		them	
	-examine	Only examine current results; do	no
		not run tests	
	-show	Run tests and show results, but do	no
		not examine them; implies -byte	
	-update	Take current results as new oracles;	no
		do not run tests	
Misc.	-exclude suite	Do not consider the given suite	
	-diff cmd	Use cmd to show differences between	diff -u
		results and oracles when examining	
		results	
	-cmp cmd	Use cmd to compare results against	cmp -s
		oracles when examining results	
	-use-diff-as-cmp	Use the same command for diff and	no
		cmp	
	-j n	Set level of parallelism to n	4
	-v	Increase verbosity (up to twice)	0
	-help	Display helps	no

Figure 4.1: ptests options.

4.5.5 Detailed directives

Figure 4.2 shows all the directives that can be used in the configuration header of a test (or a test suite). Any directive can identify a file using a relative path. The default directory considered for . is always the parent directory of directory tests. The DONTRUN and NOFRAMAC directives do not need to have any content, but it might be useful to provide an explanation of why the test should not be run (e.g test of a feature that is under development and not fully operational yet).

If there are OPT/STDOPT directives *after* a NOFRAMAC directive, they will be executed, unless they are themselves discarded by another subsequent NOFRAMAC directive.

As said in Section 4.5.2, these directives can be found in different places:

- 1. default value of the directive (as specified in Fig. 4.2);
- 2. inside file tests/test_config;

CHAPTER 4. ADVANCED PLUG-IN DEVELOPMENT

- 3. inside file tests/subdir/test_config (for each sub-directory subdir of tests); or
- 4. inside each test file

As presented in Section 4.5.3, alternative directives for test configuration <special_name> can be found in slightly different places:

- default value of the directive (as specified in Fig. 4.2);
- inside file tests/test_config_<special_name>;
- inside file tests/subdir/test_config_<special_name> (for each sub-directory subdir of tests); or
- inside each test file.

For a given test tests/suite/test.c, each existing file in the sequence above is read in order and defines a configuration level (the default configuration level always exists).

- CMD allows changing the command that is used for the following OPT directives (until a new CMD directive is found). No new test case is generated if there is no further OPT directive. At a given configuration level, the default value for directive CMD is the last CMD directive of the preceding configuration level.
- LOG adds a file to be compared against an oracle in the next OPT or STDOPT directive. Several files can be monitored from a single OPT/STDOPT directive, through several LOG directives. These files must be generated in the result directory of the corresponding suite (and potentially alternative configuration). After an OPT or STDOPT directive is encountered, the set of additional LOG files is reset to its default.
- By default, Frama-C is expected to return successfully (i.e., with an exit status of 0). If a test is supposed to lead to an error, an EXIT directive must be used. It takes as argument an integer (typically 1 to denote a user error) representing the expected exit status for the subsequent tests. All tests triggered by OPT or STDOPT directives encountered after the EXIT directive will be expected to exit with the corresponding status, until a new EXIT directive is encountered. (EXIT: 0 will thus indicate that subsequent tests are expected to exit normally).
- If there are several directives OPT in the same configuration level, they correspond to different test cases. The OPT directive(s) of a given configuration level replace(s) the ones of the preceding level.
- The STDOPT directive takes as default set of options the last OPT directive(s) of the preceding configuration level. If the preceding configuration level contains several OPT directives, hence several test cases, STDOPT is applied to each of them, leading to the same number of test cases. The syntax for this directive is the following.

STDOPT: [[+#-]"opt" ...]

options are always given between quotes. An option following a + (resp. #) is added to the end (resp. start) of current set of options while an option following a - is removed from it. The directive can be empty (meaning that the corresponding test will use the standard set of options). As with OPT, each STDOPT corresponds to a different (set of) test case(s). LOG directives preceding an STDOPT are taken into account.

• The syntax for directives **EXECNOW** and **EXEC** is the following.

EXECNOW: [[LOG file | BIN file] ...] cmd

or

EXEC: [[LOG file | BIN file] ...] cmd

Files after LOG are log files generated by command cmd and compared from oracles, whereas files after BIN are binary files also generated by cmd but not compared from oracles. Full access path to these files have to be specified only in cmd. All the commands described by directives EXECNOW or EXEC are executed in order and before running any of the other directives. If the execution of one EXECNOW or EXEC directive fails (*i.e.* has a non-zero return code), the remaining actions are not executed. EXECNOW or EXEC directives from a given level are added to the directives of the following levels.

The distinction between EXECNOW and EXEC only occurs when the command is put in a test configuration file: EXECNOW executes the command only once for the test suite, while EXEC executes it once per test file of the test suite.

• The MACRO directive has the following syntax:

MACRO: macro-name content

where macro-name is any sequence of characters containing neither a blank nor an Q, and content extends until the end of the line. Once such a directive has been encountered, each occurrence of Qmacro-nameQ in a CMD, LOG, OPT, STDOPT or EXECNOW directive at this configuration level or in any level below it will be replaced by content. Existing predefined macros are listed in section 5.3.1.

- MODULE directive takes as argument the name of a .cmxs module. It will then add a directive to compile this file with the command @PTEST_MAKE_MODULE@ <MODULE> where @PTEST_MAKE_MODULE@ defaults to make -s. Option -load-module <MODULE> will then be appended to any subsequent Frama-C command triggered by the test.
- The FILEREG directive contains a regular expression indicating which files in the directory containing the current test suite are actually part of the suite. This directive is only usable in a test_config configuration file.

• The FILTER directive specifies a transformation on the test result files before the comparison to the oracles. The filtering command read the result from the standard input and the oracle will be compared with the standard output of that command. In such a directive, the predefined macro @PTEST_ORACLE@ is set to the basename of the oracle. That allows running a diff command with the oracle of another test configuration config:

FILTER: diff --new-file @PTEST_DIR@/oracle_config/@PTEST_ORACLE@ -

Chaining multiple filter commands is possible by defining several FILTER directives (they are applied in the reverse order), and an empty command drops the previous FILTER directives.

© in the text of a directive As mentioned above, **©** is recognized by ptests as the beginning of a macro. If you need to have a literal **©** in the text of the directive itself, it needs to be doubled, *i.e.* **@©** will be translated as **©**.

Summary: ordering of test executions

There is no total ordering between the tests in a test file header. The only guaranteed order between test executions is the following:

- 1. EXEC and EXECNOW commands are executed sequentially, from top to bottom.
- 2. Then, all OPT/STDOPT commands execute in an unspecified order (possibly simultaneously).

A consequence of this ordering is that, if you need a test to produce output that will be consumed by another test, the producer *must* be defined via EXEC/EXECNOW (e.g. using @frama-c@ and explicitly giving its arguments), while the consumer can be either in a later EXEC/EXECNOW, or in a OPT/STDOPT directive.

4.6 Plug-in General Services

Module Plugin provides an access to some general services available for all plug-ins. The goal of this module is twofold. First, it helps developers to use general Frama-C services. Second, it provides to the end-user a set of features common to all plug-ins. To access to these services, you have to apply the functor Plugin.Register.

Each plug-in must apply this functor exactly once.

Example 4.10 Here is how the plug-in From applies the functor Plugin.Register for its own use.

```
include Plugin.Register
(struct
    let name = "from analysis"
    let shortname = "from"
```

```
let help = "functional dependencies"
end)
```

Applying this functor mainly provides two different services. First it gives access to functions for printing messages in a Frama-C-compliant way (see Section 4.7). Second it allows to define plug-in specific parameters available as options on the Frama-C command line to the end-user (see Section 4.12).

4.7 Logging Services

Displaying results of plug-in computations to users, warning them of the hypothesis taken by the static analyzers, reporting incorrect inputs, all these tasks are easy to think about, but turn out to be difficult to handle in a readable way. As soon as your plug-in is registered (see Section 4.6 above), though, you automatically benefit from many logging facilities provided by the kernel. What is more, when logging through these services, messages from your plug-in combine with other messages from other plug-ins, in a consistent and user-friendly way.

As a general rule, you should *never* write to standard output and error channels through OCaml standard libraries. For instance, you should never use Stdlib.stdout and Stdlib.stderr channels, nor Format.printf-like routines.

Instead, you should use Format.fprintf to implement pretty-printers for your own complex data, and only the printf-like routines of Log.Messages to display messages to the user. All these routines are immediately available from your plug-in general services.

Example 4.11 A minimal example of a plug-in using the logging services:

```
module Self = Plugin.Register
(struct
    let name = "foo plugin"
    let shortname = "foo"
    let help = "illustration of logging services"
    end)
let pp_dg out n =
Format.fprintf out
    "you have at least debug %d" n
let run () =
    Self.result "Hello, this is Foo Logs !";
    Self.debug ~level:0 "Try higher debug levels (%a)" pp_dg 0;
    Self.debug ~level:1 "If you read this, %a." pp_dg 1;
    Self.debug ~level:3 "If you read this, %a." pp_dg 3;
let () = Db.Main.extend run ()
```

Running this example, you should see:

\$ frama-c -foo-debug 2
[foo] Hello, this is Foo Logs !
[foo] Try higher debug levels (you have at least debug 0).
[foo] If you read this, you have at least debug 1.

Notice that your plug-in automatically benefits from its own debug command line parameter, and that messages are automatically prefixed with the name of the plug-in. We now get into more details for an advanced usage of logging services.

4.7.1 From printf to Log

Below is a simple example of how to make a printf-based code towards being Log-compliant. The original code, extracted from the Occurrence plug-in in Frama-C-Lithium version is as follows:

```
let print_one v l =
Format.printf "variable %s (%d):@\n" v.vname v.vid;
List.iter
  (fun (ki, lv) →
     Format.printf " sid %a: %a@\n" d_ki ki d_lval lv)
  l
let print_all () =
  compute ();
  Occurrences.iter print_one
```

The transformation is straightforward. First you add to all your pretty-printing functions an additional Format.formatter parameter, and you call fprintf instead of printf:

```
let print_one fmt v l =
Format.fprintf fmt "variable %s (%d):@\n" v.vname v.vid;
List.iter
  (fun (ki, lv) →
      Format.fprintf fmt " sid %a: %a@\n" d_ki ki d_lval lv)
  l
```

Then, you delegate toplevel calls to printf towards an appropriate logging routine, with a formatting string containing the necessary "%t" and "%a" formatters:

```
let print_all () =
  compute ();
  result "%t" (fun fmt → Occurrences.iter (print_one fmt))
```

4.7.2 Log Quick Reference

The logging routines for your plug-ins consist in an implementation of the Log.Messages interface, which is included in the Plugin.S interface returned by the registration of your plug-in. The main routines of interest are:

```
result < options> "..."
```

Outputs most of your messages with this routine. You may specify \sim level :n option to discard too detailed messages in conjunction with the *verbose* command line option. The default level is 1.

$f\!eedback <\!\mathit{options}\!\!>"\dots"$

Reserved for *short* messages that gives feedback about the progression of long computations. Typically, entering a function body or iterating during fixpoint computation. The level option can be used as for result.

debug *< options>* "..."

To be used for plug-in development messages and internal error diagnosis. You may specify ~level:n option to discard too detailed messages in conjunction with the *debug* command line option. The default message level is 1, and the default debugging level is 0. Hence, without any option, debug discards all its messages.

warning *< options*> "..."

For reporting to the user an important information about the validity of the analysis performed by your plug-in. For instance, if you locally assume non arithmetic overflow on a given statement, *etc.* Typical options include ~current:true to localize the message on the current source location.

error *< options*> "..."

```
abort <options> "..."
```

Use these routines for reporting to the user an error in its inputs. It can be used for non valid parameters, for instance. It should *not* be used for some not-yet implemented feature, however.

The abort routine is a variant that raises an exception and thus immediately aborts the computation⁵. If you use error, execution will continue until the end of current stage or current group of the running phase (see section 4.13).

```
failure < options> "..."
```

```
fatal <options> "..."
```

Use these routines for reporting to the user that your plug-in is now in inconsistent state or can not continue its computation. Typically, you have just discovered a bug in your plug-in!

The fatal routine is a variant that raises an exception. failure has a behavior similar to error above, except that it denotes an internal error instead of a user error.

```
verify (condition) < options> "..."
```

First the routine evaluates the condition and the formatting arguments, then, discards the message if the condition holds and displays a message otherwise. Finally, it returns the condition value.

A typical usage is for example:

assert (verify (x> 0) "Expected a positive value (%d)" x)

4.7.3 Logging Routine Options

Logging routines have optional parameters to modify their general behavior. Hence their involved type in Log.mli.

Level Option. A minimal level of verbosity or debugging can be specified for the message to be emitted. For the result and feedback channels, the verbosity level is used ; for the debug channel, the debugging level is used.

~level : n minimal level required is n.

⁵The raised exception is not supposed to be caught by anything else than the main entry point of Frama-C.

Category Option Debug, result, and feedback output can be associated to a debugging key with the optional argument ~dkey which takes an argument of abstract type category. Each category must be registered through the register_category function. You can define subcategories by putting colons in the registered name. For instance a:b:c defines a subcategory c of a:b, itself a subcategory of a. User can then choose to output debugging messages belonging to a given category (and its subcategories) with the -plugin-msg-key < category> option.

In order to decide whether a message should be output, both level and category options are examined:

- if neither ~level nor ~dkey, the effect is the same as having a level of 1 and no category.
- if only ~level is provided, the message is output if the corresponding verbosity or debugging level is sufficient
- if only ~dkey is used, the message is output if the corresponding category is in used (even if the verbosity or debugging level is 0)
- if both ~level and ~dkey are present, the message is output if the two conditions above (sufficient verbosity or debugging level and appropriate category in use) hold. As a rule of thumb, you should refrain from using both mechanisms to control the output of a message. If some messages of a category do not have the same importance, use subcategories to give the user a finer control on what they want to see on the output.

Warning Category Option Warning output can also be associated with a category, via the ~wkey optional argument that takes a value of abstract type warn_category. Warning categories are distinct from plain categories, and must be registered with the register_warn_category function. As explained in the user manual [3], each category can be associated with a status that controls what will happen when a warning is triggered, from completely ignoring it to aborting execution. The default is to emit the warning, but this can be changed by using the set_warn_status function.

Source Options. By default, a message is not localized. You may specify a source location, either specifically or by using the current location of an AST visitor.

~source: s use the source location s (see Log.mli)

~current:true use the current source location managed by Cil.CurrentLoc.

Emission Options. By default, a message is echoed to the user *after* its construction, and it is sent to registered callbacks when emitted. See Section 4.7.4 below for more details on how to globally modify such a behavior. During the message construction, you can locally modify the emission process with the following options:

~emitwith: f suppresses the echo and sends the emitted event *only* to the callback function f. Listeners are not fired at all.

 $\sim \! {\rm once:true}$ finally discards the message if the same one was already emitted before with the $\sim \! {\rm once}$ option.

Append Option. All logging routines have the \sim append: f optional parameter, where f is function taking a Format.formatter as parameter and returning unit. This function f is invoked to append some text to the logging routine. Such continuation-passing style is sometime necessary for defining new polymorphic formatting functions. It has been introduced for the same purpose than standard Format.kfprintf-like functions.

4.7.4 Advanced Logging Services

Message Emission

During message construction, the message content is echoed in the terminal. This echo may be delayed until message completion when ~once has been used. Upon message completion, the message is *emitted* and sent to all globally registered hook functions, unless the ~emitwith option has been used.

To interact with this general procedure, the plug-in developer can use the following functions defined in module Log:

val set_echo: ?plugin:string \rightarrow ?kinds:kind list \rightarrow bool \rightarrow unit val add_listener: ?plugin:string \rightarrow ?kinds:kind list \rightarrow (event \rightarrow unit) \rightarrow unit

Continuations

The logging routines take as argument a (polymorphic) formatting string, followed by the formatting parameters, and finally return unit. It is also possible to catch the generated message, and to pass it to a continuation that finally returns a value different than unit.

For this purpose, you must use the with_<log> routines variants. These routines take a continuation f for additional parameter. After emitting the corresponding message in the normal way, the message is passed to the continuation f. Hence, f has type $event \rightarrow \alpha$, and the log routine returns α .

For instance, you typically use the following code fragment to return a degenerated value while emitting a warning:

```
let rec fact n =

if (n> 12) then

with_warning (fun _ \rightarrow 0) "Overflow for %d, return 0 instead" x

else if n \leq 1 then 1 else n * fact (n-1)
```

Generic Routines

The Log. Messages interface provides two generic routines that can be used instead of the basic ones:

log ?kind ?verbose ?debug < options> "..."

Emits a message with the given kind, when the verbosity and/or debugging level are sufficient.

with_log f ?kind <options> "..."

Emits a message like log, and finally pass the generated message to the continuation f, and returns its result.

The default kind is Result, but all the other kind of message can be specified. For verbosity and debugging levels, the message is emitted when:

log ""	verbosity is at least 1
$\log \sim verbose: n$	verbosity is at least n
$\log \sim \text{debug}: n$	debugging is at least n
$\log \sim verbose: v \sim debug: d$	<i>either</i> verbosity is at least v
	or debugging is at least d .

Channel Management

The logging services are build upon *channels*, which are basically buffered formatters to standard output extended with locking, delayed echo, and notification services.

The very safe feature of logging services is that recursive calls *are* protected. A message is only echoed upon termination, and a channel buffer is stacked only if necessary to preserve memory.

Services provided at plug-in registration are convenient shortcuts to low-level logging service onto channels. The Log interface allows you to create such channels for your own purposes.

Basically, *channels* ensure that no message emission interfere with each others during echo on standard output. Hence the forbidden direct access to Stdlib.stdout. However, Log interface allows you to create such channels on your own, in addition to the one automatically created for your plug-in.

$\mathbf{new_channel} \ name$

This creates a new channel. There is only one channel *per* name, and the function returns the existing one if any. Plug-in channels are registered under their short-name, and the kernel channel is registered under Log.kernel_channel_name.

log_channel channel ?kind ?prefix

This routine is similar to the log one.

with_log_channel channel f ?kind ?prefix This routine is similar to the with_log one.

With both logging routines, you may specify a prefix to be used during echo. The available switches are:

Label t: use the string t as a prefix for the first echoed line of text, then use an indentation of same length for the next lines.

Prefix t: use the string t as a prefix for all lines of text.

Indent n: use an indentation of n spaces for all lines of text.

When left unspecified, the prefix is computed from the message kind and the channel name, like for plug-ins.

4.8. THE DATATYPE LIBRARY: TYPE VALUES AND DATATYPES

Output Management

It is possible to ask Log to redirect its output to another channel:

set_output out flush

The parameters are the same than those of Format.make_formatter: out outputs a (sub)string and flush actually writes the buffered text to the underlying device.

It is also possible to have a momentary direct access to Stdlib.stdout, or whatever its redirection is:

print_on_output "..."

The routine immediately locks the output of Log and prints the provided message. All message echoes are delayed until the routine actually returns. Notification to listeners is not delayed, however.

print_delayed "..."

This variant locks the output *only* when the first character would be written to output. This gives a chance to a message to be echoed before your text is actually written.

Remark that these two routines can *not* be recursively invoked, since they have a lock to a nondelayed output channel. This constraint is verified at runtime to avoid incorrect interleaving, and you would get a fatal error if the situation occurs.

Warning: these routine are dedicated to *expensive* output only. You get the advantage of not buffering your text before printing. But on the other hand, if you have messages to be echoed during printing, they must be stacked until the end of your printing.

You get a similar functionality with Kernel_function.CodeOutput.output. This routine prints your text by calling Log.print_delayed, unless the command line option -ocode has been set. It this case, your text is written to the specified file.

4.8 The Datatype library: Type Values and Datatypes

Type values and datatypes are key notions of Frama-C. They are both provided by the Datatype library. An overview as well as technical details may also be found in a related article in French [18]. A short summary focusing on (un)marshaling is described in another article [6]. First, Section 4.8.1 introduces type values. Then Section 4.8.2 introduces datatypes built on top of type values.

4.8.1 Type Value

A type value is an OCaml value which dynamically represents a static monomorphic OCaml type τ . It gets the type τ Type.t. There is at most one type value which represents the type τ . Type values are used by Frama-C to ensure safety when dynamic typing is required (for instance to access to a dynamic plug-in API, see Section 4.9.3).

Type values for standard OCaml monomorphic types are provided in module Datatype.

Example 4.12 The type value for type int is Datatype.int while the one for type string is Datatype.string. The former has type int Type.t while the latter has type string Type.t.

Type values are created when building datatypes (see Section 4.8.2). There is no type value for polymorphic types. Instead, they have to be created for each instance of a polymorphic type. Functions for accessing such type values for standard OCaml polymorphic types are provided in moduleDatatype.

Example 4.13 The type value for type int list is Datatype.list Datatype.int while the one for type string \rightarrow char \rightarrow bool is Datatype.func2 Datatype.string Datatype.char Datatype.bool. The former has type int list Type.t while the latter has type (string \rightarrow char \rightarrow bool) Type.t.

4.8.2 Datatype

A datatype provides in a single module a monomorphic type and usual values over it. Its signature is Datatype.S. It contains the type itself, the type value corresponding to this type, its name, functions equal, compare, hash and pretty which may respectively be used to check equality, to compare, to hash and to pretty print values of this type. It also contains some other values (for instance required when marshaling or journalizing). Whenever possible, a datatype implements an extensible version of Datatype.S, namely Datatype.S_with_collections. For a type τ , this extended signature additionally provides modules Set, Map and Hashtbl respectively implementing sets over τ , maps and hashtables indexed by elements of τ .

Datatypes for OCaml types from the standard library are provided in module Datatype, while those for AST's types are provided in module Cil_datatype. Furthermore, when a kernel module implements a datastructure, it usually implements Datatype.S.

Example 4.14 The following line of code pretty prints whether two statements are equal.

```
(* assuming the type of [stmt1] and [stmt2] is Cil_types.stmt *)
Format.fprintf
fmt (* a formatter previously defined somewhere *)
"statements %a and %a are %sequal"
Cil_datatype.Stmt.pretty stmt1
Cil_datatype.Stmt.pretty stmt2
(if Cil_datatype.Stmt.equal stmt1 stmt2 then "" else "not ")
```

Example 4.15 Module Datatype.String implements Datatype.S_with_collections. Thus you can initialize a set of strings in the following way.

let string_set =
 List.fold_left
 (fun acc s → Datatype.String.Set.add s acc)
 Datatype.String.Set.empty
 ["foo"; "bar"; "baz"]

Building Datatypes

For each monomorphic type, the corresponding datatype may be created by applying the functor Datatype.Make. In addition to the type t corresponding to the datatype, several values must be provided in the argument of the functor. These values are properly documented in the Frama-C API. The following example introduces them in a practical way.

Example 4.16 *Here is how to define in the more precise way the datatype corresponding to a simple sum type.*

```
type ab = A \mid B of int
module AB =
  Datatype. Make
    (struct
       (* the type corresponding to the datatype *)
       type t = ab
       (* the unique name of the built datatype; usually the name of the
          type *)
       let name = "ab"
       (* representants of the type: a non-empty list of values of this type. It
          is only used for safety check: the best the list represents the
          different possible physical representation of the type, the best the
          check is. *)
       let reprs = [ A; B 0 ]
       (* structural descriptor describing the physical representation of the
          type. It is used when marshaling. *)
       let structural_descr =
         Structural descr. Structure
           (Structural_desr.Sum [| [| Structural_descr.p_int |] |])
       (* equality, compare and hash are the standard OCaml ones *)
       let equal (x:t) y = x = y
       let compare (x:t) y = Stdlib.compare x y
       let hash (x:t) = Hashtbl.hash x
       (* the type ab is a standard functional type, thus copying and rehashing
          are simply identity. Rehashing is used when marshaling. *)
       let copy = Datatype.identity
       let rehash = Datatype.identity
       (* the type ab does never contain any value of type Project.t *)
       let mem_project = Datatype.never_any_project
       (* pretty printer *)
       let pretty fmt x =
         Format.pp_print_string fmt
          (match x with A \rightarrow "a" \mid B n \rightarrow "b" \ \hat{} string of int n)
       (* printer which must produce a valid OCaml value in a given
          context. It is used when journalising. *)
       let internal_pretty_code prec_caller fmt = function
         | A \rightarrow
           Type.par
             prec_caller
             Type.Basic
             fmt
             (fun fmt \rightarrow Format.pp print string fmt "A")
         | \ B \ n \ \rightarrow
           Type.par
             prec caller
             Type.Call
             fmt
             (fun fmt \rightarrow Format.fprintf fmt "B %d" n)
       (* A good prefix name to use for an OCaml variable of this type. *)
       let varname v = "ab" \hat{} (match v with A \rightarrow "_a_" | B \rightarrow "_b_")
     end)
```

Only providing an effective implementation for the values name and reprs is mandatory.

For instance, if you know that you never journalize a value of a type t, you can define the function internal_pretty_code equal to the predefined function Datatype.pp_fail. Similarly, if you never use values of type t as keys of hashtable, you can define the function hash equal to the function Datatype.undefined, and so on. To ease this process, you can also use the predefined structure Datatype.Undefined.

Example 4.17 Here is a datatype where only the function equal is provided.

```
(* the same type than the one of the previous example *)
type ab = A | B of int
module AB =
Datatype.Make
(struct
    type t = ab
    let name = "ab"
    let reprs = [ A; B 0 ]
    include Datatype.Undefined
    let equal (x:t) y = x = y
end)
```

One weakness of Datatype.Undefined is that it cannot be used in a projectified state (see Section 4.11.2) because its values cannot be serializable. In such a case, you can use the very useful predefined structure Datatype.Serializable_undefined which behaves as Datatype.Undefined but defines the values which are relevant for (un)serialization.

Datatypes of Polymorphic Types

As for type values, it is not possible to create a datatype corresponding to polymorphic types, but it is possible to create them for each of their monomorphic instances.

For building such instances, you *must* not apply the functor Datatype.Make since it will create two type values for the same type (and with the same name): that is forbidden.

Instead, you must use the functor Datatype.Polymorphic for types with one type parameter and the functor Datatype.Polymorphic2 for types with two type parameters⁶. These functors takes as argument how to build the datatype corresponding each monomorphic instance.

Example 4.18 Here is how to apply Datatype.Polymorphic corresponding to the type 'a t below.

```
type α ab = A of α | B of int
module Poly_ab =
Datatype.Polymorphic
(struct
    type α t = α ab
    let name ty = Type.name ty ^ " ab"
    let module_name = "Ab"
    let reprs ty = [ A ty ]
    let structural_descr d =
        Structural_descr.Structure
        (Structural_descr.Sum
        [| [| Structural_descr.p int |] |]
```

⁶Polymorphic3 and Polymorphic4 also exist in case of polymorphic types with 3 or 4 type parameters.

```
let mk_equal f x y = match x, y with
          | A x, A y \rightarrow f x y
          | B x, B y \rightarrow x = y
          \mid A _, B _ \mid B _, A _ \rightarrow false
       let mk\_compare f x y = match x, y with
          | A x, A y \rightarrow f x y
          | B x, B y \rightarrow Stdlib.compare x y
          | A _, B _ \rightarrow 1
          | B _, A _ \rightarrow -1
       let mk_hash f = function A x \rightarrow f x | B x \rightarrow 257 * x
       let map f = function A x \rightarrow A (f x) | B x \rightarrow B x
       let mk_internal_pretty_code f prec_caller fmt = function
        | A x \rightarrow
           Type.par
             prec caller
             Type.Basic
             \operatorname{fmt}
             (fun fmt \rightarrow Format.fprintf fmt "A %a" (f Type.Call) x)
         | B n \rightarrow
           Type.par
             prec_caller
             Type.Call
             fmt
             (fun fmt \rightarrow Format.fprintf fmt "B %d" n)
       let mk_pretty f fmt x =
        mk_internal_pretty_code (fun \_ \rightarrow f) Type.Basic fmt x
       let mk_varname _ = "ab"
       let mk_mem_project mem f = function
        | A x \rightarrow \text{mem f } x
        | B \rightarrow false
     end)
module Ab = Poly_AB.Make
(* datatype corresponding to the type [int ab] *)
module Ab_int = Ab(Datatype.Int)
(* datatype corresponding to the type [int list ab] *)
module Ab_Ab_string = Ab(Datatype.List(Datatype.Int))
(* datatype corresponding to the type [(string, int) Hashtbl.t ab] *)
module HAb = Ab(Datatype.String.Hashtbl.Make(Datatype.Int))
```

Clearly it is a bit painful. However you probably will never apply this functor yourself. It is already applied for the standard OCaml polymorphic types like list and function (respectively Datatype.List and Datatype.Function).

4.9 Plug-in Registration and Access

In this section, we present how to register plug-ins and how to access them. Actually there are three different ways, but the recommended one is through a .mli file.

Section 4.9.1 indicates how to register and access a plug-in through a .mli file. Section 4.9.2 indicates how to register and access a *kernel-integrated* plug-in while Section 4.9.3 details how to register and access a *standard* plug-in.

4.9.1 Registration through a .mli File

Target readers: plug-in developers.

Prerequisite: Basic knowledge of make.

Each plug-in is compiled into a module of name indicated by the variable PLUGIN_NAME of its Makefile (say Plugin_A. Its developer has to provide a .mli for this plug-in (following the previous example, a file Plugin_A.mli). This .mli file may thus contains the API of the plug-in.

Another plug-in may then access to Plugin_A as it accesses any other OCaml module, but it has to declare in its Makefile that it depends on Plugin_A through the special variable PLUGIN_DEPENDENCIES.

Example 4.19 *Plugin_A* declares and provides access to a function *compute* in the following way.

```
File File plugin_a/my_analysis_a.ml
```

let compute () = \dots

File File plugin_a/Plugin_A.mli

module My_analysis_a: sig val compute: unit \rightarrow unit

File File plugin_a/Makefile

```
PLUGIN_NAME:=Plugin_A
PLUGIN_CMO:=... my_analysis_a ...
include Makefile.dynamic
```

Then, Plugin_B may use this function Compute as follows.

```
File File plugin_b/my_analysis_b.ml
```

let compute () = ... Plugin_A.My_analysis_a.compute () ...

File File plugin_b/Makefile

```
PLUGIN_NAME:=Plugin_B
PLUGIN_CMO:=... my_analysis_b ...
PLUGIN_DEPENDENCIES:=Plugin_A
...
include Makefile.dynamic
```

4.9.2 Kernel-integrated Registration and Access

Target readers: kernel-integrated plug-in developers.

Prerequisite: Accepting to modify the Frama-C kernel. Otherwise, you can still register your plug-in as any standard plug-in (see Section 4.9.3 for details).

A database, called Db (in directory src/kernel_services/plugin_entry_points), groups together the API of all kernel-integrated plug-ins. So it permits easy plug-in collaborations. Each kernel-integrated plug-in is only visible through Db. For example, if a plug-in A wants to know the results of another plug-in B, it uses the part of Db corresponding to B. A consequence of this design is that each plug-in has to register in Db by setting a function pointer to the right value in order to be usable from others plug-ins.

Example 4.20 Plug-in Impact registers function compute_pragmas in the following way.

File src/plugins/impact/register.ml

let compute_pragmas () = ... let () = Db.Impact.compute_pragmas ← compute_pragmas

Thus each developer who wants to use this function calls it by pointer dereferencing like this.

let () = !Db.Impact.compute_pragmas ()

If a kernel-integrated plug-in has to export some datatypes usable by other plug-ins, such datatypes have to be visible from module Db. Thus they cannot be declared in the plug-in implementation itself like any other plug-in declaration because postponed type declarations are not possible in OCaml.

Such datatypes are called *plug-in types*. The solution is to put these plug-ins types in some files linked before Db; hence you have to put them in another directory than the plug-in directory. The best way is to create a directory dedicated to types.

Recommendation 4.2 The suggested name for this directory is p_types for a plug-in p.

If you add such a directory, you also have to modify Makefile by extending variable FRAMAC_SRC_DIRS (see Section 5.2.3).

Example 4.21 Suppose you are writing a plug-in p which exports a specific type t corresponding to the result of the plug-in analysis. The standard way to proceed is the following.

```
File src/plugins/p_types/p_types.mli
```

```
type t = ...
```

File src/kernel_services/plugin_entry_points/db.mli

File share/Makefile.common

FRAMAC_SRC_DIRS= ... plugins/p_types
 # Extend this variable with the new directory

This design choice has a side effect : it reveals exported types. You can always hide them using a module to encapsulate the types (and provide corresponding getters and setters to access them).

At this point, part of the plug-in code is outside the plug-in implementation. This code should be linked before Db^{7} .

To this effect, the files containing the external plug-in code must be added to the Makefile variable PLUGIN_TYPES_CMO (see Section 5.2.3).

4.9.3 Dynamic Registration and Access

Target readers: standard plug-ins developers.

Registration of kernel-integrated plug-ins requires to modify module Db which belongs to the Frama-C kernel. Such a modification is not possible for standard plug-ins which are fully independent of Frama-C. Consequently, the Frama-C kernel provides another way for registering a plug-in through the module Dynamic.

In short, you have to use the function Dynamic.register in order to register a value from a dynamic plug-in and you have to use function Dynamic.get in order to apply a function previously registered with Dynamic.register.

Registering a value

The signature of Dynamic.register is as follows.

```
val register : plugin : string \to string \to \alpha Type.t \to journalize : bool \to \alpha \to unit
```

The first argument is the name of the plug-in registering the value and the second one is a binding name of the registered OCaml value. The pair (plug-in name, binding name) must not be used for value registration anywhere else in Frama-C. It is required in order for another plug-in to access to this value (see next paragraph). The third argument is the *type value* of the registered value (see Section 4.8.1). It is required for safety reasons when accessing to the registered value (see the next paragraph). The labeled fourth argument journalize indicates whether a total call to this function must be written in the journal (see also Section 4.10). The usual value for this argument is true. The fifth argument is the value to register.

Example 4.22 Here is how the function run of the plug-in hello of the tutorial is registered. The type of this function is unit \rightarrow unit.

```
let run () : unit = ...
let () =
Dynamic.register
~plugin:"Hello"
"run"
(Datatype.func Datatype.unit Datatype.unit)
~journalize:true
run
```

 $^{^7\}mathrm{A}$ direct consequence is that you cannot use the whole $\mathsf{Frama-C}$ functionalities, such as module $\mathtt{Db},$ inside this code.

If the string "Hello.run" is already used to register a dynamic value, then the exception Type.AlreadyExists is raised during plug-in initialization (see Section 4.13).

The function call Datatype.func Datatype.unit Datatype.unit returns the type value representing unit \rightarrow unit. Note that, because of the type of Dynamic.register and the types of its arguments, the OCaml type checker complains if the third argument (here the value run) has not the type unit \rightarrow unit.

Accessing to a registered value

The signature of function Dynamic.get is as follows.

```
| val get: plugin: string \rightarrow string \rightarrow \alpha Type.t \rightarrow \alpha
```

The arguments must be the same than the ones used at value registration time (with Dynamic.register). Otherwise, depending on the case, you will get a compile-time or a runtime error.

Example 4.23 Here is how the previously registered function run of Hello may be applied.

```
let () =
  Dynamic.get
  ~plugin:"Hello"
  "run"
  (Datatype.func Datatype.unit Datatype.unit)
  ()
```

The given strings and the given type value must be the same than the ones used when registering the function. Otherwise, an error occurs at runtime. Furthermore, the OCaml type checker will complain either if the third argument (here ()) is not of type unit or if the returned value (here () also) is not of type unit.

The above-mentioned mechanism requires access to the type value corresponding to the type of the registered value. Thus it is not possible to access a value of a plug-in-defined type. For solving this issue, Frama-C provides a way to access type values of plug-in-defined types in an abstract way through the functor Type.Abstract.

Example 4.24 There is no current example in the Frama-C open-source part, but consider a plug-in which provides a dynamic API for callstacks as follows.

```
module P =
Plugin.Register
(struct
    let name = "Callstack"
    let shortname = "Callstack"
    let help = "callstack library"
    end)
(* A callstack is a list of a pair (kf * stmt) where [kf] is the kernel
    function called at statement [stmt]. Building the datatype also creates the
    corresponding type value [ty]. *)
type callstack = (Kernel_function.t * Cil_datatype.Stmt.t) list
(* Implementation *)
let empty = []
```

CHAPTER 4. ADVANCED PLUG-IN DEVELOPMENT

```
let push kf stmt stack = (kf, stmt) :: stack
let pop = function [] \rightarrow [] | _ :: stack \rightarrow stack
let rec print = function
 | [] \rightarrow P.feedback ""
  | (kf, stmt) :: stack \rightarrow
   P.feedback "function %a called at stmt %a"
     Kernel function.pretty kf
      Cil datatype.Stmt.pretty stmt;
    print stack
(* Type values *)
let kf_ty = Kernel_function.ty
let stmt_ty = Cil_datatype.Stmt.ty
module D =
 Datatype.Make
    (struct
      type t = callstack
      let name = "Callstack.t"
      let reprs = [ empty; [ Kernel_function.dummy (), Cil.dummyStmt ] ]
      include Datatype.Serializable_undefined
    end)
(* Dynamic API registration *)
let register name ty =
 Dynamic.register ~plugin:"Callstack" ~journalize:false name ty
let empty = register "empty" D.ty empty
let push = register "push" (Datatype.func3 kf_ty stmt_ty D.ty D.ty) push
let pop = register "pop" (Datatype.func D.ty D.ty) pop
```

let print = register "print" (Datatype.func D.ty Datatype.unit) print

You have to use the functor Type.Abstract to access to the type value corresponding to the type of callstacks (and thus to access to the above dynamically registered functions).

```
(* Type values *)
let kf_ty = Kernel_function.ty
let stmt ty = Cil datatype.Stmt.ty
(* Access to the type value for abstract callstacks *)
module C = Type.Abstract(struct let name = "Callstack.t" end)
let get name ty = Dynamic.get ~plugin:"Callstack" name ty
(* mutable callstack *)
let callstack ref = ref (get "empty" C.ty)
(* operations over this mutable callstack *)
let push callstack =
  (* getting the function outside the closure is more efficient *)
  let push = get "push" (Datatype.func3 kf_ty stmt_ty C.ty C.ty) in
  fun kf stmt \rightarrow callstack_ref \leftarrow push kf stmt !callstack_ref
let pop callstack =
  (* getting the function outside the closure is more efficient *)
 let pop = get "pop" (Datatype.func C.ty C.ty) in
```

```
fun () → callstack_ref ← pop !callstack_ref
let print_callstack =
  (* getting the function outside the closure is more efficient *)
  let print = get "print" (Datatype.func C.ty Datatype.unit) in
  fun () → print !callstack_ref
  (* ... algorithm using the callstack ... *)
```

4.10 Journalization

Not written yet: please report as "feature request" on http://bts.frama-c.com if you really need this section.

4.11 Project Management System

Prerequisite: *Knowledge of the* OCaml *module system and labels.*

In Frama-C, a key notion detailed in this section is the one of *project*. An overview as well as technical details may also be found in a related article in French [17]. Section 4.11.1 first introduces the general principle of project. Section 4.11.2 introduces the notion of *states*. State registration is detailed in Sections 4.11.3 and 4.11.4. The former is dedicated to standard (high-level) registration, while the latter is dedicated to low-level registration. Then Section 4.11.5 explains how to use projects. Finally Section 4.11.6 details state selections.

4.11.1 Overview and Key Notions

A *project* groups together an AST with the set of global values attached to it. Such values are called *states*. Examples of states are parameters (see Section 4.12) and results of analyses (Frama-C extensively uses memoization [14, 15] in order to prevent running analyses twice).

In a Frama-C session, several projects (and thus several ASTs) can exist at the same time. The project library ensures project non-interference: modifying the value of a state in a project does not impact any value of any state in any other project. To ensure this property, each state must be registered in the project library as explained in Sections 4.11.3 and 4.11.4. Relations between states and projects are summarized in Figure 4.3.

To ease development, Frama-C maintains a current project (Project.current ()): all operations are automatically performed on it. For instance, calling Ast.get () returns the Frama-C AST of the current project. It is also possible to access values in others projects as explained in Section 4.11.5.

4.11.2 State: Principle

If some data should be part of the state of Frama-C, you must register it in the project library (see Sections 4.11.3 and 4.11.4).

Here we first explain what are the functionalities of each state and then we present the general principle of registration.

State Functionalities

Whenever you want to attach some data (e.g. a table containing results of an analysis) to an AST, you have to register it as an internal state. The main functionalities provided to each internal state are the following.

- It is automatically updated whenever the current project changes. Your data are thus always consistent with the current project. More precisely, you still work with your global data (for instance, a hashtable or a reference) as usual in OCaml. The project library silently changes the data when required (usually when the current project is changing). The extra cost due to the project system is usually an extra indirection. Figure 4.4 summarizes these interactions between the project library and your state.
- It is part of the information saved on disk for restoration in a later session.
- It may be part of a *selection* which is a consistent set of states. With such a selection, you can control on which states project operations are consistently applied (see Section 4.11.6). For example, it is possible to clear all the states which depend on Value Analysis results.
- It is possible to ensure inter-analysis consistency by setting state dependencies. For example, if the entry point of the analyzed program is changed (using Globals.set_entry_point), all the results of analyses depending on it (like value analysis' results) are automatically reset. If such a reset were not performed, the results of the value analysis would not be consistent anymore with the current entry point, leading to incorrect results.

Example 4.25

!Db.Value.compute(); Kernel.feedback "%B" (Db.Value.is_computed ()); (* true *) Globals.set_entry_point "f" true; Kernel.feedback "%B" (Db.Value.is_computed ()); (* false *)

As the value analysis has been automatically reset when setting the entry point, the above code outputs

[kernel] true [kernel] false

State Registration: Overview

For registering a new state, functor State_builder.Register is provided. Its use is described in Section 4.11.4 but it is a low-level functor which is usually difficult to apply in a correct way. Higher-level functors are provided to the developer in modules State_builder and Cil_state_builder that allow the developer to register states in a simpler way. They internally apply the low-level functor in the proper way. Module State_builder provides state builders for standard OCaml datastructures like hashtables whereas Cil_state_builder does the same for standard Cil datastructures (like hashtables indexed by AST statements)⁸. They are described in Section 4.11.3.

 $^{^{8}{\}rm These}$ data structures are only mutable data structures (like hashtables, arrays and references) because global states are always mutable.

Registering a new state must be performed when the plugin is initialized. Thus, using OCaml let module construct to register the new state is forbidden (except if you really know what you are doing).

4.11.3 Registering a New State

Here we explain how to register and use a state. Registration through the use of the low-level functor **State_builder.Register** is postponed in Section 4.11.4 because it is more tricky and rarely useful.

In most non-Frama-C applications, a state is a global mutable value. One can use it to store results of analyses. For example, using this mechanism inside Frama-C to create a state which would memoize some information attached to statements would result in the following piece of code.

```
open Cil_datatype
type info = Kernel_function.t * Cil_types.varinfo
let state : info Stmt.Hashtbl.t = Stmt.Hashtbl.create 97
let compute_info (kf,vi) = ...
let memoize s =
   try Stmt.Hashtbl.find state s
   with Not_found → Stmt.Hashtbl.add state s (compute_info s)
let run () = ... !Db.Value.compute (); ... memoize some_stmt ...
```

However, if one puts this code inside Frama-C, it does not work because this state is not registered as a Frama-C state. For instance, it is never saved on the disk and its value is never changed when setting the current project to a new one. For this purpose, one has to transform the above code into the following one.

```
module State =
   Cil_state_builder.Stmt_hashtbl
    (Datatype.Pair(Kernel_function)(Cil_datatype.Varinfo))
    (struct
        let size = 97
        let name = "state"
        let dependencies = [ Db.Value.self ]
        end)
let compute_info (kf,vi) = ...
let memoize = State.memo compute_info
let run () = ... !Db.Value.compute (); ... memoize some_stmt ...
```

A quick look on this code shows that the declaration of the state itself is more complicated (it uses a functor application) but its use is simpler. Actually what has changed?

1. To declare a new internal state, apply one of the predefined functors in modules State_builder or Cil_state_builder (see interfaces of these modules for the list of available modules). Here we use Cil_state_builder.Stmt_hashtbl which provides a hashtable indexed by statements. The type of values associated to statements is a pair of Kernel_function.t and Cil_types.varinfo. The first argument of the functor is then the datatype corresponding to this type (see Section 4.8.2). The second argument provides some additional information: the initial size of the hashtable (an integer similar to the argument of Hashtbl.create), an unique name for the resulting state and its dependencies. This list of dependencies is built upon values self which are called

state kind (or simply *kind*) and are part of any state's module (part of the signature of the low-level functor State_builder.Register). This value represents the state itself as first-class value (like type values for OCaml types, see Section 4.8.1).

2. From outside, a state actually hides its internal representation in order to ensure some invariants: operations on states implementing hashtables do not take hashtables as arguments because they implicitly use the hidden hashtable. In our example, a predefined memo function is used in order to memoize the computation of compute_info. This memoization function implicitly operates on the hashtable hidden in the internal representation of State.

Postponed dependencies Sometimes, you want to access a state kind before defining it. That is usually the case when you have two mutually-dependent states: the dependencies of the first one provided when registering it must contain the state kind of the second one which is created by registering it. But this second registration also requires a list of dependencies containing the first state kind.

For solving this issue, it is possible to postpone the addition of a state kind to dependencies until all modules have been initialized. However, dependencies must be correct before any-thing serious is computed by Frama-C. So the right way to do this is the use of the function Cmdline.run_after_extended_stage (see Section 4.13 for advanced explanation about the way Frama-C is initialized).

Example 4.26 Plug-in from puts a reference to its state kind in the following way. This reference is initialized at module initialization time.

```
File src/kernel_services/plugin_entry_points/db.mli
```

```
module From = struct
...
val self: State.t ref
end
```

File src/kernel_services/plugin_entry_points/db.ml

```
module From = struct
...
val self = ref State.dummy (* postponed *)
end
```

File src/plugins/from/functionwise.ml

```
module Tbl =
   Kernel_function.Make_Table
   (Function_Froms)
   (struct
        let name = "functionwise_from"
        let size = 97
        let dependencies = [ Db.Value.self ]
        end)
let () =
   (* performed at module initialization runtime. *)
   Db.From.self ← Tbl.self
```

Plug-in pdg uses from for computing its own internal state. So it declares this dependency as follows.

```
File src/plugins/pdg/register.ml
```

Dependencies over the AST Most internal states depend directly or indirectly on the AST of the current project. However, the AST plays a special role as a state. Namely, it can be changed in place, bypassing the project mechanism. In particular, it is possible to add globals. Plugins that perform such changes should inform the kernel when they are done using Ast.mark_as_changed or Ast.mark_as_grown. The latter must be used when the only changes are additions, leaving existing nodes untouched, while the former must be used for more intrusive changes. In addition, it is possible to tell the kernel that a state is "monotonic" with respect to AST changes, in the sense that it does not need to be cleared when nodes are added (the information that should be associated to the new nodes will be computed as needed). This is done with the function Ast.add_monotonic_state. Ast.mark_as_grown will not touch such a state, while Ast.mark_as_changed will clear it.

4.11.4 Direct Use of Low-level Functor State_builder.Register

Functor State_builder.Register is the only functor which really registers a state. All the others internally use it. In some cases (*e.g.* if you define your own mutable record used as a state), you have to use it. Actually, in the Frama-C kernel, there are only three direct uses of this functor over thousands of state registrations: so you will certainly never use it.

This functor takes three arguments. The first and the third ones respectively correspond to the datatype and to information (name and dependencies) of the states: they are similar to the corresponding arguments of the high-level functors (see Section 4.11.3).

The second argument explains how to handle the *local version* of the state under registration. Indeed here is the key point: from the outside, only this local version is used for efficiency purposes (remember Figure 4.4). It would work even if projects do not exist. Each project knows a *global version*. The project management system *automatically* switches the local version when the current project changes in order to conserve a physical equality between local version and current global version. So, for this purpose, the second argument provides a type t (type of values of the state) and five functions create (creation of a new fresh state), clear (cleaning a state), get (getting a state), set (setting a state) and clear_some_projects (how to clear each value of type project in the state if any).

The following invariants must hold:⁹

c

create () returns a fresh value (4.1	L)	1
--------------------------------------	----	---

(4.3)

```
\forall p \text{ of type t, create () = (clear p; set p; get ())} (4.2)
```

 $\forall p \text{ of type t, copy } p \text{ returns a fresh value}$

```
\forall p1, p2 \text{ of type t such that } p1 != p2, (set p1; get ()) != p2 (4.4)
```

Invariant 4.1 ensures that there is no sharing with any value of a same state: so each new project has got its own fresh state. Invariant 4.2 ensures that cleaning a state resets it to its initial value. Invariant 4.3 ensures that there is no sharing with any copy. Invariant 4.4 is a local independence criterion which ensures that modifying a local version does not affect any other version (different from the global current one) by side effects.

Example 4.27 To illustrate this, we show how functor State_builder.Ref (registering a state corresponding to a reference) is implemented.

```
module Ref
 (Data: Datatype.S)
 (Info: sig include Info val default: unit → Data.t end) =
struct
 type data = Data.t
  let create () = ref Info.default
  let state = ref (create ())
```

Here we use an additional reference: our local version is a reference on the right value. We can use it in order to safely and easily implement get and set required by the registration.

```
include Register
(Datatype.Ref(Data))
(struct
type t = data ref (* we register a reference on the given type *)
let create = create
let clear tbl = tbl ← Info.default
let get () = !state
let set x = state ← x
let clear_some_projects f x =
if Data.mem_project f !x then begin clear x; true end else false
end)
(Info)
```

For users of this module, we export "standard" operations which hide the local indirection required by the project management system.

```
let set v = !state ← v
let get () = !(!state)
let clear () = !state ← Info.default
end
```

As you can see, the above implementation is error prone; in particular it uses a double indirection (reference of reference). So be happy that higher-level functors like State_builder.Ref are provided which hide such implementations from you.

 9 As usual in OCaml, = stands for *structural* equality while == (resp. !=) stands for *physical* equality (resp. disequality).

4.11.5 Using Projects

As said before, all operations are done by default on the current project. But sometimes plugin developers have to explicitly use another project, for example when the AST is modified (usually through the use of a copy visitor, see Section 4.17) or replaced (*e.g.* if a new one is loaded from disk).

An AST must never be modified inside a project. If such an operation is required, you must either create a new project with a new AST, usually by using File.init_project_from_cil_file or File.init_project_from_visitor; or write the following line of code (see Section 4.11.6):

```
let selection = State_selection.only_dependencies Ast.self in
Project.clear ~selection ()
```

Operations over projects are grouped together in module Project. A project has type Project.t. Function Project.set_current sets the current project on which all operations are implicitly performed.

Example 4.28 Suppose that you saved the current project into file foo.sav in a previous Frama-C session¹⁰ thanks to the following instruction.

```
Project.save "foo.sav"
```

In a new Frama-C session, executing the following lines of code (assuming the value analysis has never been computed previously)

```
let print_computed () =
   Kernel.feedback "%B" (Db.Value.is_computed ())
in
print_computed (); (* false *)
let old = Project.current () in
try
   let foo = Project.load ~name:"foo" "foo.sav" in
   Project.set_current foo;
   !Db.Value.compute ();
   print_computed (); (* true *)
   Project.set_current old;
   print_computed () (* false *)
with Project.IOError _ →
   Kernel.abort "error while loading"
```

displays

[kernel] false [kernel] true [kernel] false

This example shows that the value analysis has been computed only in project foo and not in project old.

An important invariant of Frama-C is: if p is the current project before running an analysis, then p will be the current project after running it. It is the responsibility of any plug-in developer to enforce this invariant for his/her own analysis.

¹⁰A session is one execution of Frama-C (through frama-c or frama-c-gui).

To be sure to enforce the above-mentioned invariant, the project library provides an alternative to the use of Project.set_current: Project.on applies an operation on a given project without changing the current project (*i.e.* locally switch the current project in order to apply the given operation and, afterwards, restore the initial context).

Example 4.29 The following code is equivalent to the one given in Example 4.28.

```
let print_computed () =
Value_parameters.feedback "%B" (Db.Value.is_computed ())
in
print_computed (); (* false *)
try
    let foo = Project.load ~name:"foo" "foo.sav" in
    Project.on foo
        (fun () → !Db.Value.compute (); print_computed () (* true *)) ();
    print_computed () (* false *)
with Project.IOError _ →
    exit 1
```

It displays

false true false

4.11.6 Selections

Most operations working on a single project (*e.g.* Project.clear or Project.on) have an optional parameter selection of type State_selection.t. This parameter allows the developer to specify on which states the operation applies. A *selection* is a set of states which allows the developer to consistently handle state dependencies.

Example 4.30 The following statement clears all the results of the value analysis and all its dependencies in the current project.

let selection = State_selection.with_dependencies Db.Value.self in Project.clear ~ selection ()

The selection explicitly indicates that we also want to clear all the states which depend on the value analysis' results.

Use selections carefully: if you apply a function f on a selection s and f handles a state which does not belong to s, then the computed result by Frama-C is potentially incorrect.

Example 4.31 The following statement applies a function f in the project p (which is not the current one). For efficiency purposes, we restrict the considered states to the command line options (see Section 4.12).

Project.on ~selection:(Parameter_state.get_selection ()) p f ()

This statement only works if f only handles values of the command line options. If it tries to get the value of another state, the result is unspecified and all actions using any state of the current project and of project p also become unspecified.

4.12 Command Line Options

Prerequisite: Knowledge of the OCaml module system.

Values associated with command line options are called *parameters*. The parameters of the Frama-C kernel are stored in module Kernel while the plug-in specific ones have to be defined in the plug-in source code.

4.12.1 Definition

In Frama-C, a parameter is represented by a value of type Typed_parameter.t and by a module implementing the signature Parameter_sig.S. The first representation is a low-level one required by emitters (see Section 4.18) and the GUI. The second one provides a high-level API: each parameter is indeed a state (see Section 4.11.2). Several signatures extending Parameter_sig.S are provided in order to deal with the usual parameter types. For example, there are signatures Parameter_sig.Int and Parameter_sig.Bool for integer and boolean parameters. Mostly, these signatures provide getters and setters for modifying parameter values.

Implementing such an interface is very easy thanks to a set of functors provided by the output module of Plugin.Register. Indeed, you have just to choose the right functor according to your option type and potentially the wished default value. Below are some examples of such functors (see the signature Parameter_sig.Builder for an exhaustive list).

- 1. False (resp. True) builds a boolean option initialized to false (resp. true).
- 2. Int (resp. Zero) builds an integer option initialized to a specified value (resp. to 0).
- 3. String (resp. Empty_string) builds a string option initialized to a specified value (resp. to the empty string "").
- 4. String_set builds an option taking a set of strings in argument (initialized to the empty set).
- 5. Kernel_function_set builds an option taking a set of kernel functions in argument (initialized to the empty set).

Each functor takes as argument (at least) the name of the command line option corresponding to the parameter and a short description for this option.

Example 4.32 The parameter corresponding to the option -occurrence of the plug-in occurrence is the module Print (defined in the file src/plugins/occurrence/options.ml). It is implemented as follows.

```
module Print =
False
(struct
    let option_name = "-occurrence"
    let help = "print results of occurrence analysis"
end)
```

So it is a boolean parameter initialized by default to false. The declared interface for this module is simply

module Print: Parameter_sig.Bool

Another example is the parameter corresponding to the option -impact-pragma of the plug-in impact. This parameter is defined by the module Pragma (defined in the file src/plugins/impact/options.ml). It is implemented as follows.

```
module Pragma =
   Kernel_function_set
   (struct
        let option_name = "-impact-pragma"
        let arg_name = "f1, ..., fn"
        let help = "use the impact pragmas in the code of functions f1,...,fn"
        end)
```

Thus it is a set of kernel_functions initialized by default to the empty set. Frama-C uses the field arg_name in order to print the name of the argument when displaying help. The field help is the help message itself. The Interface for this module is simple:

module Pragma: Parameter_sig.Kernel_function_set

Recommendation 4.3 Parameters of a same plug-in plugin should belong to a module called Options, Plugin_options, Parameters or Plugin_parameters inside the plug-in directory.

Using a kernel parameters or a parameter of your own plug-in is very simple: you have simply to call the function **get** corresponding to your parameter.

Example 4.33 To know whether Frama-C uses unicode, just write

Kernel.Unicode.get ()

Inside the plug-in From, just write

From_parameters.ForceCallDeps.get ()

in order to know whether callsite-wise dependencies have been required.

Using a parameter of a plug-in p in another plug-in p' requires the use of module Dynamic.Parameter: since the module defining the parameter is not visible from the outside of its plug-in, you have to use the dynamic API of plug-in p in which p's parameters are automatically registered (see Section 4.9.3). The module Dynamic.Parameter defines sub-modules which provide easy access to parameters according to their OCaml types.

Example 4.34 Outside the plug-in From, just write

Dynamic.Parameter.Bool.get "-calldeps" ()

in order to know whether callsite-wise dependencies have been required.

4.12.2 Tuning

It is possible to modify the default behavior of command line options in several ways by applying functions just before or just after applying the functor defining the corresponding parameter.

Functions which can be applied afterwards are defined in the output signature of the applied functor.

Example 4.35 *Here is how the option "-slicing-level" restricts the range of its argument to the interval* [0;3].

```
module Calls =
Int
  (struct
    let option_name = "-slicing-level"
    let default = 2
    let arg_name = ""
    let help = "..." (* skipped here *)
    end)
let () = Calls.set range ~min:0 ~max:3
```

Functions which can be applied before applying the functor are defined in the module Parameter_customize.

Example 4.36 Here is how the opposite of option "-safe-arrays" is renamed into "-unsafearrays" (otherwise, by default, it would be "-no-safe-arrays").

4.13 Initialization Steps

Prerequisite: Knowledge of linking of OCaml files.

In a standard way, Frama-C modules are initialized in the link order which remains mostly unspecified, so you have to use side-effects at module initialization time carefully.

This section details the different stages of the Frama-C boot process to help advanced plug-in developers interact more deeply with the kernel process. It can also be useful for debugging initialization problems.

As a general rule, plug-in routines must never be executed at link time. Any useful code, be it for registration, configuration or C-code analysis, should be registered as *function hooks* to be executed at a proper time during the Frama-C boot process. In general, registering and executing a hook is tightly coupled with handling the command line parameters.

The parsing of the command line parameters is performed in several *phases* and *stages*, each one dedicated to specific operations. For instance, journal replays should be performed after loading dynamic plug-ins, and so on. Following the general rule stated at the beginning of this section, even the kernel services of Frama-C are internally registered as hooks routines to be executed at a specific stage of the initialization process, among plug-ins ones.

From the plug-in developer point of view, the hooks are registered by calling the run_after_xxx_stage routines in Cmdline module and extend routine in the Db.Main module.

CHAPTER 4. ADVANCED PLUG-IN DEVELOPMENT

The initialization phases and stages of Frama-C are described below, in their execution order.

- A The Initialization Stage: this stage initializes Frama-C compilation units, following some *partially* specified order. More precisely:
 - 1. the architecture dependencies depicted on Figure 3.1 (cf. p. 41) are respected. In particular, the kernel services are linked first, *then* the kernel integrated types for plug-ins, and *finally* the plug-ins are linked in unspecified order;
 - 2. when the GUI is present, for any plug-in p, the non-gui modules of p are always linked *before* the gui modules of p;
 - 3. finally, the module Boot is linked at the very end of this stage.

Plug-in developers cannot customize this stage. In particular, the module Cmdline (one of the first linked modules, see Figure 3.1) performs a very early configuration stage, such as checking if journalization has to be activated (cf. Section 4.10), or setting the global verbosity and debugging levels.

B – The Early Stage: this stage initializes the kernel services. More precisely:

- (a) first, the journal name is set to its right value (according to the option -journal-name) and the default project is created;
- (b) then, the parsing of command line options registered for the Cmdline.Early stage;
- (c) finally, all functions registered through Cmdline.run_after_early_stage are executed in an unspecified order.
- C **The Extending Stage:** the searching and loading of dynamically linked plug-ins, of journal, scripts and modules is performed at this stage. More precisely:
 - (a) the command line options registered for the Cmdline.Extending stage are treated, such as -load-script and -add-path;
 - (b) the hooks registered through Cmdline.run_during_extending_stage are executed. Such hooks include kernel function calls for searching, loading and linking the various plug-ins, journal and scripts compilation units, with respect to the command line options parsed during stages B and C.
- D The Running Phase: the command line is split into several groups of command line arguments, each of them separated by an option -then or an option -then-on p (thus if there is n occurrences of -then or -then-on p, then there are n+1 groups). For each group, the following stages are executed in sequence: all the stages are executed on the first group provided on the command line, then they are executed on the second group, and so on.
 - 1. The Extended Stage: this step is reserved for commands which require that all plug-ins are loaded but which must be executed very early. More precisely:
 - (a) the command line options registered for the Cmdline.Extended stage are treated, such as -verbose-* and -debug-*;
 - (b) the hooks registered through Cmdline.run_after_extended_stage. Most of these registered hooks come from postponed internal-state dependencies (see Section 4.11.3).

4.14. CUSTOMIZING THE AST CREATION

Remark that both statically and dynamically linked plug-ins have been loaded at this stage. Verbosity and debug level for each plug-in are determined during this stage.

- 2. The Exiting Stage: this step is reserved for commands that make Frama-C exit before starting any analysis at all, such as printing help information:
 - (a) the command line options registered for the Cmdline.Exiting stage are treated;
 - (b) the hooks registered through Cmdline.run_after_exiting_stage are executed in an unspecified order. All these functions should do nothing (using Cmdline.nop) or raise Cmdline.Exit for stopping Frama-C quickly.
- 3. The Loading Stage: this is where the initial state of Frama-C can be replaced by another one. Typically, it would be loaded from disk through the -load option or computed by running a journal (see Section 4.10). As for the other stages:
 - (a) first, the command line options registered for the Cmdline.Loading stage are treated;
 - (b) then, the hooks registered through Cmdline.run_after_loading_stage are executed in an unspecified order. These functions actually change the initial state of Frama-C with the specified one. The Frama-C kernel verifies as far as possible that only one new-initial state has been specified.

Normally, plug-ins should never register hooks for this stage unless they actually set a different initial state than the default one. In such a case:

They must call the function Cmdline.is_going_to_load while initializing.

- 4. The Configuring Stage: this is the usual place for plug-ins to perform special initialization routines if necessary, *before* having their main entry points executed. As for previous stages:
 - (a) first, the command line options registered for the Cmdline.Configuring stage are treated. Command line parameters that do not begin by a hyphen (character '-') are *not* options and are treated as C files. Thus they are added to the list of files to be preprocessed or parsed for building the AST (on demand);
 - (b) then, the hooks registered through Cmdline.run_after_configuring_stage are executed in an unspecified order.
- 5. The Setting Files Stage: this stage sets the C files to analyze according to those indicated on the command line. More precisely:
 - (a) first, each argument of the command line which does not begin by a hyphen (character '-') is registered for later analysis;
 - (b) then, the hooks registered through Cmdline.run_after_setting_files are executed in an unspecified order.
- 6. The Main Stage: this is the step where plug-ins actually run their main entry points registered through Db.Main.extend. For all intents and purposes, you should consider that this stage is the one where these hooks are executed.

4.14 Customizing the AST creation

Prerequisite: None.

Plug-ins may modify the way source files are transformed into the AST over which the analyses are performed. Customization of the front-end of Frama-C can be done at several stages.

- A Parsing: this stage takes care of converting an individual source file into a parsed AST (a.k.a Cabs, which differs from the type-checked AST on which most analyses operate). By default, source files are treated as C files, possibly needing a pre-processing phase. It is possible to tell Frama-C to use another parser for files ending with a given suffix by registering this parser with the File.new_file_type function. Suffixes .h, .i, .c and .ci are reserved for Frama-C kernel. The registered parser is supposed to return a pair consisting of a type-checked AST (Cil_types.file) and a parsed AST (Cabs.file). The former can be obtained from the latter with the Cabs2cil.convFile function, which guarantees that the resulting Cil_types.file respects all invariants expected by the Frama-C kernel.
- B **Type-checking:** a normal **Cabs.file** (*i.e.* not obtained through a custom parsing function) can be transformed before being type-checked. Transformation hooks are registered through **Frontc.add_syntactic_transformation**.
- C After linking: Once all source files have been processed, they are all linked together in a single AST. Transformations can be performed on the resulting AST at two stages:
 - 1. before clean-up (*i.e.* removal of useless temporary variables and prototypes that are never called). At that stage, global tables indexing information related to the AST have not yet been filled.
 - 2. after clean-up. At this stage, index tables are filled, and can thus be used. On the other hand, the transformation must take care itself of keeping in sync the AST and the tables

Registering a transformation for this stage is done through the function File.add_code_transformation_before_cleanup (respectively File.add_code_transformation_after_cleanup). If such a transformation modify the control-flow graph of a function f, in particular by adding statements, it must call File.must_recompute_cfg, in order to have the graph recomputed afterwards.

4.15 Customizing the machine model

Prerequisite: None.

Several aspects of the C standard that are implementation-defined, such as the width of standard integer types, endianness, signedness of the **char** type, etc., as well as a few compiler and architecture specific features, can be customized using a **machdep** configuration, defining a new machine model.

To create a new machine model, define an instance of Cil_types.mach. You can base it on the examples available in tests/misc/custom_machdep/custom_machdep.ml and src/kernel_internals/runtime/machdeps.ml. The new definition can be added to Frama-C's database using File.new_machdep.

Example 4.37 A custom machine description may be implemented as follows (the meaning of each field is presented later in this section):

```
let my_machine =
{
    version = "generic C compiler for my machine";
```

4.15. CUSTOMIZING THE MACHINE MODEL

```
= "generic";
  compiler
  cpp_arch_flags = [];
  sizeof_short
                   = 2;
  sizeof int
                   = 4;
  sizeof_long
                   = 4;
  sizeof_longlong = 8;
  sizeof ptr
                   = 4;
  sizeof float
                   = 4:
  sizeof double
                  = 8;
  size of longdouble = 12;
  sizeof void
                   = 1;
  sizeof fun
                   = 1:
  size_t = "unsigned long";
  wchar t = "int";
  ptrdiff t = "int";
  alignof_short = 2;
  alignof int = 4;
  alignof long = 4;
  alignof_longlong = 4;
  alignof_ptr = 4;
  alignof_float = 4;
  alignof_double = 4;
  alignof longdouble = 4;
  alignof\_str = 1;
  alignof_fun = 1;
  alignof\_aligned = 16;
  char_is_unsigned = false;
  const_string_literals = true;
  little endian = true;
 underscore name = false;
 has___builtin_va_list = true;
}
let () = File.new_machdep "my_machine" my_machine
```

After this code is loaded, Frama-C can be instructed to use the new machine model using the -machdep command line option.

If you intend to use Frama-C's standard library headers, you must also do the following:

- define constant __FC_MACHDEP_<CUSTOM>, replacing <CUSTOM> with the name (in uppercase letters) of your created machdep; this can be done via -cpp-extra-args="-D_FC_MACHDEP_<CUSTOM>";
- provide a header file with macro definitions corresponding to your OCaml definitions. For the most part, these are macros prefixed by __FC_, corresponding to standard C macro definitions, *e.g.*, __FC_UCHAR_MAX. These definitions are used by Frama-C's <limits.h> and other headers to provide the standard C definitions. The test file tests/misc/custom_machdep/__fc_machdep_custom.h (reproduced below) contains a complete example of the required definitions. Other examples can be found in share/libc/__fc_machdep.h.

Make sure that your custom header defines the __FC_MACHDEP include guard, and that the program you are analyzing includes this header before all other headers. One way to ensure this without having to modify any source files is to use an option such as -include in GCC.

Example 4.38 Contents of tests/misc/custom_machdep/__fc_machdep_custom.h, used as example for creating custom machdeps. Notice the unusual size for int (3 bytes), selected for testing purposes only, and inconsistent with the chosen values for INT_MIN and INT_MAX, which do not fit in 3 bytes.

```
/* skeleton of a real custom machdep header.
  Note: the values provided here are merely for illustrative purposes
        and are not necessarily consistent between them. */
\#ifndef \_FC\_MACHDEP
\#define __FC_MACHDEP
#ifdef __FC_MACHDEP_CUSTOM
/* Constants required by the C standard */
#undef CHAR UNSIGNED
#define __WORDSIZE 32
#define __SIZEOF_SHORT 2
#define __SIZEOF_INT 3
\#define __SIZEOF_LONG 4
\#define __SIZEOF_LONGLONG 8
#define \__CHAR_BIT 8
#define \_PTRDIFF_T int
#define __SIZE_T unsigned int
#define __FC_SCHAR_MIN (-128)
#define __FC_SCHAR_MAX 127
\#define __FC_UCHAR_MAX 255
#define __FC_SHRT_MIN (-32768)
#define __FC_SHRT_MAX 32767
#define __FC_USHRT_MAX 65535
#define __FC_INT_MIN (-2147483647 - 1)
#define __FC_INT_MAX 2147483647
#define FC UINT MAX 4294967295U
#define __FC_LONG_MIN (-2147483647L -1L)
#define __FC_LONG_MAX 2147483647L
\#define __FC_ULONG_MAX 4294967295UL
#define __FC_LLONG_MIN (-9223372036854775807LL -1LL)
#define __FC_LLONG_MAX 9223372036854775807LL
#define __FC_ULLONG_MAX 18446744073709551615ULL
#define __INT_MAX_T signed long long
#define __UINT_MAX_T unsigned long long
#define __FC_PATH_MAX 256
#define __FC_SIZE_MAX __FC_ULLONG_MAX
/* Optional constants */
#define __INT8_T signed char
\#define __UINT8_T unsigned char
#define __INT16_T signed short
#define __UINT16_T unsigned short
#define __INTPTR_T signed long
#define __UINTPTR_T unsigned long
#define __INT32_T signed long
#define __UINT32_T unsigned long
```

```
#define __INT64_T signed long long
#define __UINT64_T unsigned long long
/* Required constants */
\#define __INT_LEAST8_T signed char
\#define __UINT_LEAST8_T unsigned char
#define INT LEAST16 T signed short
#define UINT LEAST16 T unsigned short
#define __INT_LEAST32_T signed long
#define __UINT_LEAST32_T unsigned long
#define __INT_LEAST64_T signed long long
#define __UINT_LEAST64_T unsigned long long
#define __INT_FAST8_T signed char
#define __UINT_FAST8_T unsigned char
\#define __INT_FAST16_T signed int
#define __UINT_FAST16_T unsigned int
#define __INT_FAST32_T signed long
#define __UINT_FAST32_T unsigned long
#define __INT_FAST64_T signed long long
#define __UINT_FAST64_T unsigned long long
/* POSIX */
#define __SSIZE_T int
/* stdio.h */
\#define __FC_L_tmpnam 1024
/* stdint.h */
#define __FC_PTRDIFF_MIN __FC_INT_MIN
#define FC PTRDIFF MAX FC INT MAX
#define __FC_INTMAX_MIN (-9223372036854775807LL -1LL)
#define __FC_INTMAX_MAX 9223372036854775807LL
#define __FC_UINTMAX_MAX 18446744073709551615ULL
#define __FC_EOF (-1)
\#define __FC_FOPEN_MAX 20
#define __FC_RAND_MAX 32767
#define __WCHAR_T unsigned short
/* for stdarg.h */
#define __FC_VA_LIST_T char*
/* for time.h */
#define __FC_TIME_T long
/* for wchar.h */
\#define __WINT_T unsigned int
#define __FC_WEOF (0xFFFFFFFU)
#define __FC_WINT_MIN 0
#define __FC_WINT_MAX __FC_UINT_MAX
/* for errno.h */
\#define __FC_EPERM 1
#define \_FC\_ENOENT 2
#define __FC_ESRCH 3
```

CHAPTER 4. ADVANCED PLUG-IN DEVELOPMENT

$\#$ defineFC_EINTR 4
$\#$ defineFC_EIO 5
#defineFC_ENXIO 6
#defineFC_E2BIG 7
$\#$ defineFC_ENOEXEC 8
$\#$ defineFC_EBADF 9
$\#$ defineFC_ECHILD 10
$#$ defineFC_EAGAIN 11
#defineFC_ENOMEM 12
#defineFC_EACCES 13
#defineFC_EFAULT 14
$\#\texttt{define \FC_ENOTBLK 15}$
$\#$ defineFC_EBUSY 16
$\#$ defineFC_EEXIST 17
$#$ defineFC_EXDEV 18
#defineFC_ENODEV 19
$\#$ defineFC_EISDIR 21
$\#$ defineFC_EINVAL 22
$\#$ defineFC_ENFILE 23
$\#$ defineFC_EMFILE 24
#defineFC_ENOTTY 25
#defineFC_ETXTBSY 26
#defineFC_EFBIG 27
$\#$ defineFC_ENOSPC 28
$\#$ defineFC_ESPIPE 29
$\#$ defineFC_EROFS 30
$\#$ defineFC_EMLINK 31
$\#$ defineFC_EPIPE 32
#defineFC_ERANGE 34
$\#$ defineFC_EDEADLK 35
$\#\texttt{define}$ FC_ENAMETOOLONG 36
$\#$ defineFC_ENOLCK 37
$\#$ defineFC_ENOSYS 38
#defineFC_ENOTEMPTY 39
#defineFC_ELOOP 40
#defineFC_EWOULDBLOCK EAGAIN
#defineFC_ENOMSG 42
$\#$ defineFC_EIDRM 43
$\#\texttt{define _FC_ECHRNG 44}$
$\#$ defineFC_EL2NSYNC 45
$\#$ defineFC_EL3HLT 46
$\#$ defineFC_EL3RST 47
#defineFC_ELNRNG 48
#defineFC_EUNATCH 49
#defineFC_ENOCSI 50
$\#$ defineFC_EL2HLT 51
$\#$ defineFC_EBADE 52
$\#$ defineFC_EBADR 53
#defineFC_EXFULL 54
#defineFC_ENOANO 55
#defineFC_EBADRQC 56
#defineFC_EBADSLT 57
$\#$ defineFC_EDEADLOCK EDEADLK
$\#$ defineFC_EBFONT 59

4.15. CUSTOMIZING THE MACHINE MODEL

 $#define _FC_ENOSTR 60$ #define __FC_ENODATA 61 #define __FC_ETIME 62 #define __FC_ENOSR 63 #define __FC_ENONET 64 $#define _FC_ENOPKG 65$ #define FC EREMOTE 66 #define FC ENOLINK 67 $#define _FC_EADV 68$ #define __FC_ESRMNT 69 #define __FC_ECOMM 70 #define __FC_EPROTO 71 #define __FC_EMULTIHOP 72 #define __FC_EDOTDOT 73 #define __FC_EBADMSG 74 #define __FC_EOVERFLOW 75 #define __FC_ENOTUNIQ 76 #define __FC_EBADFD 77 $#define _FC_EREMCHG 78$ #define __FC_ELIBACC 79 #define __FC_ELIBBAD 80 #define __FC_ELIBSCN 81 #define FC ELIBMAX 82 #define __FC_ELIBEXEC 83 $#define _FC_EILSEQ 84$ #define __FC_ERESTART 85 $#define __FC_ESTRPIPE 86$ $#define _FC_EUSERS 87$ #define __FC_ENOTSOCK 88 #define FC EDESTADDRREQ 89 $#define __FC_EMSGSIZE 90$ #define __FC_EPROTOTYPE 91 #define __FC_ENOPROTOOPT 92 #define __FC_EPROTONOSUPPORT 93 #define __FC_ESOCKTNOSUPPORT 94 #define __FC_ENOTSUP 95 #define __FC_EOPNOTSUPP 95 #define __FC_EPFNOSUPPORT 96 #define __FC_EAFNOSUPPORT 97 #define __FC_EADDRINUSE 98 #define FC EADDRNOTAVAIL 99 #define __FC_ENETDOWN 100 #define __FC_ENETUNREACH 101 #define __FC_ENETRESET 102 #define __FC_ECONNABORTED 103 #define FC ECONNRESET 104 $#define _FC_ENOBUFS 105$ #define __FC_EISCONN 106 #define __FC_ENOTCONN 107 #define __FC_ESHUTDOWN 108 #define __FC_ETOOMANYREFS 109 #define __FC_ETIMEDOUT 110 #define __FC_ECONNREFUSED 111 $#define _FC_EHOSTDOWN 112$ #define __FC_EHOSTUNREACH 113 #define __FC_EALREADY 114

```
#define __FC_EINPROGRESS 115
#define __FC_ESTALE 116
#define __FC_EUCLEAN 117
\#define __FC_ENOTNAM 118
#define __FC_ENAVAIL 119
\#define __FC_EISNAM 120
#define FC EREMOTEIO 121
#define FC EDQUOT 122
#define __FC_ENOMEDIUM 123
#define __FC_EMEDIUMTYPE 124
\#define __FC_ECANCELED 125
#define \_FC\_ENOKEY 126
\#define __FC_EKEYEXPIRED 127
#define __FC_EKEYREVOKED 128
#define __FC_EKEYREJECTED 129
\#define __FC_EOWNERDEAD 130
#define __FC_ENOTRECOVERABLE 131
#define __FC_ERFKILL 132
#define __FC_EHWPOISON 133
#else
 error "I'm supposed to be called with __FC_MACHDEP_CUSTOM macro defined"
#endif
\#\texttt{endif}
```

An example of the complete command-line is presented below, for a custom machdep called myarch, defined in file my_machdep.ml and with stdlib constants defined in machdep_myarch.h:

```
frama-c -load-script my_machdep.ml -machdep myarch \
    -cpp-extra-args="-D_FC_MACHDEP_MYARCH -include machdep_myarch.h"
```

4.16 Machdep record fields

Each field in the machdep record is succintly described in the Cil_types module. We present below a thorough description of each field.

version : human-readable textual description of the machdep.

compiler : defines whether special compiler-specific extensions will be enabled. It should be one of the strings below:

msvc : enables Cil.msvcMode, that is, MSVC (Visual Studio)-specific extensions;

gcc : enables Cil.gccMode, that is, GCC-specific extensions;

generic (or any other string): no special compiler-specific extensions.

Note that some compiler extensions, such as attributes, are always enabled.

cpp_arch_flags : list of arguments to be added to the command-line when invoking the C preprocessor. Typically used to ensure that multiarch compilers apply the appropriate

predefined macros¹¹. E.g. use ["-m32"] for a 32-bit machdep when preprocessing with a 64-bit multiarch GCC. Note that, in practice, very few programs rely on such predefined macros, such as $_x86_{64}$ and $_i386$.

sizeof_short : size (in bytes) of the short type.

sizeof_int : size (in bytes) of the int type.

sizeof_long : size (in bytes) of the long type.

- sizeof_longlong : size (in bytes) of the long long type. Note that machdeps (for compiler
 "gcc" in particular) must always have at least one type that is 8 bytes wide, which is
 typically long long.
- sizeof_ptr : size (in bytes) of an object (non-function) pointer.
- sizeof_float : size (in bytes) of a single-precision floating point. In implementations compliant with ISO/IEC/IEEE 60559 -IEEE 754, this is always 4.
- sizeof_double : size (in bytes) of a double-precision floating point. In implementations compliant with ISO/IEC/IEEE 60559 - IEEE 754, this is always 8.
- sizeof_longdouble : size (in bytes) of a long double floating point. Note: type
 long double is currently not supported by existing Frama-C plugins, but this field
 exists for future expansion, and to compute sizeof of aggregates properly.
- **sizeof_void** : the result of evaluating **sizeof(void)** by the compiler (or 0 if unsupported).
- size_t : a string containing the actual type that size_t expands to, e.g. "unsigned long".
- ptrdiff_t : a string containing the actual type that ptrdiff_t expands to. If unsupported, you can use int.
- alignof_short : the result of evaluating _Alignof(short).
- alignof_int : the result of evaluating _Alignof(int).
- alignof_long : the result of evaluating _Alignof(long).

alignof_longlong : the result of evaluating _Alignof(long long).

- alignof_ptr : the result of evaluating _Alignof(char*) (or any other pointer, including function pointers).
- alignof_float : the result of evaluating _Alignof(float).
- alignof_double : the result of evaluating _Alignof(double).

alignof_longdouble : the result of evaluating _Alignof(long double).

¹¹Note that the sizes of standard integer types are already defined in the machdep, so they do not depend on these flags.

alignof_str : the result of evaluating _Alignof("a") (a literal string).

- alignof_aligned : the default alignment of a type having the aligned attribute (or 1 if unsupported). This corresponds to the default alignment when using #pragma packed() without a numeric argument.
- char_is_unsigned : whether type char is unsigned.
- const_string_literals : whether string literals have const chars, or are writable.
 If true, the following code has undefined behavior, otherwise it is defined:
 char *s = "no"; s[0] = 'g';.
- little_endian : whether the machine is little endian.
- underscore_name : whether the compiler generates assembly labels by prepending _ to the identifier. That is, will function foo() have the label foo, or _foo?
- has_builtin_va_list : whether __builtin_va_list is a (built-in) type known by the
 preprocessor.
- __thread_is_keyword : whether __thread is a keyword (otherwise, it can be used as a standard identifier).

Writing a new machdep Writing a machdep for a new architecture is not trivial, due to the fact that some steps are hard to automate. If you have a working compiler for the target architecture, you can use it to produce an executable that will print the contents of expressions such as sizeof(long), _Alignof(int), etc. You can also use the compiler to test for unsupported features. In case printf is not available, you can use the exit code of the program (return code of main). In case you can only preprocess, but not compile and run the program, the assembly code may provide some useful data.

4.17 Visitors

Prerequisite: *Knowledge of* OCaml *object programming.*

Module Cil offers a visitor, Cil.cilVisitor, that allows to traverse (parts of) an AST. It is a class with one method per type of the AST, whose default behavior is simply to call the method corresponding to its children. This is a convenient way to perform local transformations over a whole Cil_types.file by inheriting from it and redefining a few methods. However, the original Cil visitor is of course not aware of the internal state of Frama-C itself. Hence, there exists another visitor, Visitor.generic_frama_c_visitor, which handles projects in a transparent way for the user. There are very few cases where the plain Cil visitor should be used.

Basically, as soon as the initial project has been built from the C source files (*i.e.* one of the functions File.init_* has been applied), only the Frama-C visitor should occur.

There are a few differences between the two (the Frama-C visitor inherits from the Cil one). These differences are summarized in Section 4.17.6, which the reader already familiar with Cil is invited to read carefully.

4.17. VISITORS

4.17.1 Entry Points

Module Cil offers various entry points for the visitor. They are functions called Cil.visitCilAstType where astType is a node type in the Cil's AST. Such a function takes as argument an instance of a cilVisitor and an astType and gives back an astType transformed according to the visitor. The entry points for visiting a whole Cil_types.file (Cil.visitCilFileCopy, Cil.visitCilFile and visitCilFileSameGlobals) are slightly different and do not support all kinds of visitors. See the documentation attached to them in cil.mli for more details.

4.17.2 Methods

As said above, there is a method for each type in the Cil AST (including for logic annotation). For a given type astType, the method is called $vastType^{12}$, and has type $astType \rightarrow astType'$ visitAction, where astType' is either astType or astType list (for instance, one can transform a global into several ones). visitAction describes what should be done for the children of the resulting AST node, and is presented in the next section. In addition, some types have two modes of visit: one for the declaration and one for use. This is the case for varinfo (vvdec and vvrbl), logic_var (vlogic_var_decl and vlogic_var_use) logic_info (vlogic_info_decl and vlogic_info_use), logic_type_info (vlogic_type_info_decl and vlogic_type_info_decl and vlogic_ctor_info_decl information can be found in cil.mli.

For the Frama-C visitor, two methods, vstmt and vglob take care of maintaining the coherence between the transformed AST and the internal state of Frama-C. Thus they must not be redefined. One should redefine vstmt_aux and vglob_aux instead.

4.17.3 Action Performed

The return value of visiting methods indicates what should be done next. There are six possibilities:

- SkipChildren the visitor does not visit the children;
- ChangeTo v the old node is replaced by v and the visit stops;
- DoChildren the visit goes on with the children; this is the default behavior;
- JustCopy is only meaningful for the copy visitor. Indicates that the visit should go on with the children, but only perform a fresh copy of the nodes
- ChangeToPost(v,f) the old node is replaced by v, and f is applied to the result. This is however not exactly the same thing as returning ChangeTo(f(v)). Namely, in the case of vglob_aux, f will be applied to v only *after* the operations needed to maintain the consistency of Frama-C's internal state with respect to the AST have been performed. Thus, ChangeToPost should be used with extreme caution, as f could break some invariants of the kernel.

 $^{^{12}{\}rm This}$ naming convention is not strictly enforced. For instance the method corresponding to offset is voffs.

- DoChildrenPost f visit the children and apply the given function to the result.
- JustCopyPost(f) is only meaningful for the copy visitor. Performs a fresh copy of the nodes and all its children and applies f to the copy.
- ChangeDoChildrenPost(v,f) the old node is replaced by v, the visit goes on with the children of v, and when it is finished, f is applied to the result. In the case of vstmt_aux, f is called after the annotations in the annotations table have been visited, but *before* they are attached to the new statement, that is, they will be added to the result of f. Similarly, vglob_aux will consider the result of f when filling the table of globals. Note that ChangeDoChildrenPost(x,f) where x is the current node is *not* equivalent to DoChildrenPost f, as in the latter case, the visitor mechanism knows that it still deals with the original node.

4.17.4 Visitors and Projects

Copy visitors (see next section) implicitly take an additional argument, which is the project in which the transformed AST should be put in.

Note that the tables of the new project are not filled immediately. Instead, actions are queued, and performed when a whole Cil_types.file has been visited. One can access the queue with the get_filling_actions method, and perform the associated actions on the new project with the fill_global_tables method.

In-place visitors always operate on the current project (otherwise, two projects would risk sharing the same AST).

4.17.5 In-place and Copy Visitors

The visitors take as argument a visitor_behavior, which comes in two flavors: inplace_visit and copy_visit. In the in-place mode, nodes are visited in place, while in the copy mode, nodes are copied and the visit is done on the copy. For the nodes shared across the AST (varinfo, compinfo, enuminfo, typeinfo, stmt, logic_var, logic_info and fieldinfo), sharing is of course preserved, and the mapping between the old nodes and their copy can be manipulated explicitly through the following functions:

- reset_behavior_name resets the mapping corresponding to the type name.
- get_original_*name* gets the original value corresponding to a copy (and behaves as the identity if the given value is not known).
- get_name gets the copy corresponding to an old value. If the given value is not known, it behaves as the identity.
- **set**_*name* sets a copy for a given value. Be sure to use it before any occurrence of the old value has been copied, or sharing will be lost.

get_original_name functions allow to retrieve additional information tied to the original AST nodes. Its result must not be modified in place (this would defeat the purpose of operating on a copy to leave the original AST untouched). Moreover, note that whenever the index used for *name* is modified in the copy, the internal state of the visitor behavior must be updated accordingly (*via* the set_name function) for get_original_name to give correct results.

The list of such indices is given Figure 4.5.

Last, when using a copy visitor, the actions (see previous section) SkipChildren and ChangeTo must be used with care, *i.e.* one has to ensure that the children are fresh. Otherwise, the new AST will share some nodes with the old one. Even worse, in such a situation the new AST might very well be left in an inconsistent state, with uses of shared node (*e.g.* a varinfo for a function f in a function call) which do not match the corresponding declaration (*e.g* the GFun definition of f).

When in doubt, a safe solution is to use JustCopy instead of SkipChildren and ChangeDoChildrenPost(x,fun $x \rightarrow x$) instead of ChangeTo(x).

4.17.6 Differences Between the Cil and Frama-C Visitors

As said in Section 4.17.2, vstmt and vglob should not be redefined. Use vstmt_aux and vglob_aux instead. Be aware that the entries corresponding to statements and globals in Frama-C tables are considered more or less as children of the node. In particular, if the method returns ChangeTo action (see Section 4.17.3), it is assumed that it has taken care of updating the tables accordingly, which can be a little tricky when copying a file from a project to another one. Prefer ChangeDoChildrenPost. On the other hand, a SkipChildren action implies that the visit will stop, but the information associated to the old value will be associated to the new one. If the children are to be visited, it is undefined whether the table entries are visited before or after the children in the AST.

4.17.7 Example

Here is a small copy visitor that adds an assertion for each division in the program, stating that the divisor is not zero:

```
open Cil types
open Cil
module M = Plugin.Register
(* Each annotation in Frama-C has an emitter, for traceability.
   We create thus our own, and says that it will only be used to emit code
  annotations, and that these annotations do not depend
  on Frama-C's command line parameters.
*)
let syntax alarm =
 Emitter.create
   "Syntactic check" [ Emitter.Code annot ] ~correctness:[] ~tuning:[]
class non_zero_divisor prj = object (self)
  inherit Visitor .generic_frama_c_visitor (Visitor_behavior .copy prj)
  (* A division is an expression: we override the vexpr method *)
 method! vexpr e = match e.enode with
  | BinOp((Div|Mod), _, denom, _) \rightarrow
    let logic_denom = Logic_utils.expr_to_term ~coerce:false denom in
    let assertion = Logic_const.prel (Rneq, logic_denom, Cil.lzero ()) in
   (* At this point, we have built the assertion we want to insert. It remains
      to attach it to the correct statement. The cil visitor maintains the
```

```
information of which statement and function are currently visited in
       the [current_stmt] and [current_kf] methods, which return None when
       outside of a statement or a function, e.g. when visiting a global
       declaration. Here, it necessarily returns [Some]. *)
    let stmt = match self#current_kinstr with
      \mid Kglobal \rightarrow assert false
      | Kstmt s \rightarrow s
    in
    let kf = Option.get self#current_kf in
    (* The above statement and function are related to the original project. We
       need to attach the new assertion to the corresponding statement and
       function of the new project. Cil provides functions to convert a
      statement (function) of the original project to the corresponding
       one of the new project. *)
    let new stmt = Visitor behavior.Get.stmt self#behavior stmt in
    let new_kf = Visitor_behavior.Get.kernel_function self#behavior kf in
    (* Since we are copying the file in a new project, we cannot insert
       the annotation into the current table, but in the table of the new
       project. To avoid the cost of switching projects back and forth,
       all operations on the new project are queued until the end of the
       visit, as mentioned above. This is done in the following statement. *)
    Queue.add
      (fun () \rightarrow
        Annotations.add_assert syntax_alarm ~kf:new_kf new_stmt assertion)
      self # get_filling_actions ;
   DoChildren
  | \_ \rightarrow DoChildren
end
(* This function creates a new project initialized with the current file plus
  the annotations related to division. *)
let create_syntactic_check_project () =
  ignore
    (File.create project from visitor "syntactic check" (new non zero divisor))
let () = Db.Main.extend create_syntactic_check_project
```

4.18 Logical Annotations

Prerequisite: None.

Logical annotations set by the users in the analyzed C program are part of the AST. However others annotations (those generated by plug-ins) are not directly in the AST because it would contradict the rule "an AST must never be modified inside a project" (see Section 4.11.5).

So all the logical annotations (including those set by the users) are put in global projectified tables maintained up-to-date by the Frama-C kernel. Anytime a plug-in wants either to access to or to add/delete an annotation, it *must* use the corresponding modules or functions and not the annotations directly stored in the AST. These modules and functions are the following.

• Module Annotations which contains the database of annotations related to the AST (global annotations, function contracts and code annotations). Adding or deleting an annotation requires to define an emitter by Emitter.create first.

- Module Property_status should be used to get or to modify the validity status of logical properties. Modifying a property status requires to define an emitter by Emitter.create first. Key concepts and theoretical foundation of this module are described in an associated research paper [5].
- Module **Property** provides access to all logical properties on which property statuses can be emitted. In particular, an ACSL annotation has to be converted into a property if you want to access its property statuses.
- Modules Logic_const, Logic_utils and Db.Properties contain several operations over annotations.

4.19 Extending ACSL annotations

Prerequisite: *Knowledge of the ACSL specification language.*

Frama-C supports the possibility of adding specific ACSL annotations in the form of special clauses. Such clauses can be of different categories, as described by Cil_types.ext_category.

- A contract extension will be stored in the **b_extended** field of **Cil_types.behavior**.
- A global extension will be found as a global ACSL annotation in the form of a Cil_types.Dextended constructor.
- A code annotation extension will be stored with an Cil_types.AExtended constructor. Such an extension has itself different flavors, determined by the type:
 - it can be meant to be evaluated exactly at the current program point (like an ACSL assert), or
 - $-\,$ it can be related to the next statement (or block), like an ACSL statement contract, or
 - it can be a loop extension, or
 - it can be used both as a loop extension or be related to the next (non-loop) statement.

An extension is characterized by its introducing keyword kw, or loop kw for a loop extension. It is not possible to have the same keyword for two distinct extensions, especially if they belong to different categories, as this would lead to ambiguities in the parser.

Once an extension is registered a clause of the form $kw e1, \ldots, en;$, where each ei can be any syntactically valid ACSL term or predicate, will be treated by the parser as belonging to the extension kw.

Contract extension clauses must occur after **assumes** and **requires** clauses if any, but can be freely mixed with other behavior clauses (post-conditions, **assigns**, **frees** and **allocates**).

Similarly, in a loop annotation, loop kw e1, ..., en; will be treated as belonging to the kw extension. In case the loop annotation has a loop variant, the extension must occur before. Otherwise, there is no ordering constraint with other loop annotations clauses.

Global extensions can appear either alone in a global annotation, or as part of an axiomatic with a set of other global annotations.

Finally, a code annotation extension must appear as a single code annotation, like any code annotation.

Code (and loop) extensions can be made specific to a set of existing behaviors using the standard ACSL for construction. Namely, for bhv: loop kw e1, ..., en; will indicate that the (loop) extension is supposed to be considered only when behavior bhv is active (although it is ultimately up to the plugin to decide what to do with this information).

An acsl_extension is a triple (id, kw, ext) where id is its unique ID, used in annotation tables and generated by Logic_const.new_acsl_extension, kw identifies the extension, and ext is an acsl_extension_kind and can take three forms:

- Ext_id id with id an int that the plugin can use to refer to the annotation in its internal state. This identifier is under the full responsibility of the plugin and will never be used by the kernel.
- Ext_preds preds with preds a possibly empty list of predicates.
- Ext_terms terms with terms a possibly empty list of terms.

For the latter two cases, the corresponding list is traversed normally by the visitor (see section 4.17).

In order for the extension to be recognized by the parser, it must be registered by one of the following functions, depending on its category.

- Acsl_extension.register_behavior
- Acsl_extension.register_global
- Acsl_extension.register_code_annot
- Acsl_extension.register_code_annot_next_stmt
- Acsl_extension.register_code_annot_next_loop
- Acsl_extension.register_code_annot_next_both

Each function takes the following mandatory arguments:

- kw the name of the extension,
- typer the type-checking function itself.
- **status**, a boolean flag indicating whether the extended annotation may have a validity status, and

During type-checking, the list [e1;...;en] will be given to typer, together with the current typing environment (which allows discriminating between contract and loop extensions and will have the appropriate logic labels set in the local environment). typer must return the corresponding acsl_extension_kind (possibly adding an entry for key id in an internal table if it chooses to return Ext_id id).

The first argument of typer is a Logic_typing.typing_context which provides lookup functions for the various kinds of identifiers that are present in the environment, as well as extensible type-checking functions for predicates, terms, and assigns clauses. Indeed, these

functions take themselves as argument a typing_context ctxt and will use the functions of ctxt to type-check the children of the current node. Extensions can take advantage of this open recursion to recognize only subtrees of an otherwise normal ACSL predicate or term. For instance, the following code will let extension foo replace all occurrences of \foo by 42.

let () = Acsl_extension.register_behavior "foo" type_foo false

With this extension enabled, Frama-C will interpret the following clause in a given source file:

 $| /*@ foo 84 \equiv \foo + \foo; */$

as the following type-checked AST fragment:

 $| \ / * @ \ {
m foo} \ 84 \equiv 42 + 42; \, * /$

If the extended clause is of kind Ext_preds 1 or Ext_terms 1, and all the information of the extension is contained in the list 1, no function other than the typing function needs to be registered. The parsing will use the standard way to parse untyped predicates and terms. After typing, the visitor will traverse each element of 1 as well as any predicate or term present in the AST. The pretty-printer will output these elements as a comma-separated list preceded by kw (or loop kw if the extension is a loop annotation).

However, depending on the situation, the following optional functions can be provided to the registration function in order to modify how ACSL extensions are handled by Frama-C:

- **preprocessor** a transformer to apply on the untyped term or predicate read during the parsing phase,
- visitor the visitor function to be applied when visiting the extension,
- printer the pretty-printing function associated to the extension,
- short_printer a function used to provide a brief textual representation of an extension.

The **preprocessor** function is applied just after parsing the extension terms. It takes the list of untyped terms or predicates and can either return the same list (but reading it to do some stuff) or return a new list. By default, this function is the identity.

The visitor function is used by the Frama-C visitors. It takes the current visitor, together with the acsl_extension_kind of the extended clause and must returns a Cil.visitAction. By default, this function just returns Cil.DoChildren.

The printer function is used by the Cil_printer.pp_extended function. It takes the current pretty-printer, the formatter, together with the acsl_extension_kind of the extended clause. By default, it prints the list of terms or predicates if the kind is Ext_preds 1 or Ext_terms 1. If the kind is Ext_id i, it only prints the integer i.

The short_printer function is a function that can be useful for debugging or user-feedback. As an alternative to Cil_printer.pp_extended, the Cil_printer.pp_short_extended can be used to get brief description of the content of the extension. It is for example used by the GUI to get a more informative name for the extension in the file tree. By default, it does not print anything about the content of the extension, so that the result is "kwd" or "loop kwd".

When the extension kind is Ext_id, it is common that the plugin defining the extension contains a table that associates some data to this identifier. In such a case, a printer might be needed to reconstruct the source code from the data so that a pretty printed code can be parsed again. For the same reason, an extension that registers a preprocessor that modifies the AST should probably register a printer to recover the original content.

It is also common, when the kind is Ext_id, to define a particular visitor for the extension, either to ignore the content of the extension as it is in an internal table of the plugin (thus returning a SkipChildren action) or, on the opposite, to give the possibility to a user defined visitor to get an access to this content.

The following code shows a more complete extension example. It provides the user a way to load some types (assumed to be external to Frama-C) so that they can be used in ACSL specification.


```
open Logic_ptree
open Logic_typing
open Cil_types
let preprocessor =
  List.map (fun e \rightarrow begin match e with
      | { lexpr_node = PLnamed ("load", { lexpr_node = PLvar s}) } \rightarrow
        if not (Logic env.is logic type s) then Logic env.add typename s
        else Kernel.error "Type already exists %s" s
      | \_ \rightarrow ()
    end ; e)
module Ts = struct
  let id = ref 0
  let types = Hashtbl.create 5
  let add t = let i = !id in Hashtbl.add types i t ; id \leftarrow i + 1 ; i
  let find = Hashtbl.find types
end
let typer ctxt loc = function
  | [ { lexpr_node = PLnamed ("load", { lexpr_node = PLvar s}) } ] \rightarrow
    let ti = { lt_name = s ; lt_params = [] ; lt_def = None ; lt_attr = [] } in
    ctxt.add logic type s ti ;
   Ext_id (Ts.add ti)
  | \_ \rightarrow
    ctxt.error loc "Expected type loader"
let visitor _ _ = Cil.SkipChildren
let gen printer s pp fmt = function
```

```
| Ext_id i →
Format.fprintf fmt "%s: %s"
   (if s then "ext_type" else "load") (Ts.find i).lt_name
| _ → assert false
let printer = gen_printer false
let short_printer = gen_printer true
let () =
Acsl_extension.register_global
   "ext_type" ~preprocessor typer ~visitor ~printer ~short_printer false
```

Namely, specification:

```
/*@ ext_type load: foo ; */
/*@
axiomatic Pred {
    predicate P(foo f) reads \nothing ;
    }
*/
/*@ lemma X: \forall foo f ; P(f) ; */
```

is correctly parsed and typed by Frama-C and leads to the following displayed version in the interface:



4.20 Locations

Prerequisite: None.

In Frama-C, different representations of C locations exist. Section 4.20.1 presents them. Moreover, maps indexed by locations are also provided. Section 4.20.2 introduces them.

4.20.1 Representations

There are four different representations of C locations. Actually only three are really relevant. All of them are defined in module Locations. They are introduced below. See the documentation of src/kernel_services/abstract_interp/locations.mli for details about the provided operations on these types.

- Type Location_Bytes.t is used to represent values of C expressions like 2 or ((int) &a) + 13. With this representation, there is no way to know the size of a value while it is still possible to join two values. Roughly speaking it is represented by a mapping between C variables and offsets in bytes.
- Type location, equivalently Location.t is used to represent the right part of a C affectation (including bitfields). It is represented by a Location_Bits.t (see below) attached to a size. It is possible to join two locations *if and only if they have the same sizes*.
- Type Location_Bits.t is similar to Location_Bytes.t with offsets in bits instead of bytes. Actually it should only be used inside a location.
- Type Zone.t is a set of bits (without any specific order). It is possible to join two zones even if they have different sizes.

Recommendation 4.4 Roughly speaking, locations and zones have the same purpose. You should use locations as soon as you have no need to join locations of different sizes. If you require to convert locations to zones, use the function Locations.enumerate_valid_bits.

As join operators are provided for these types, they can be easily used in abstract interpretation analyses (which can themselves be implemented thanks to one of functors of module Dataflow2.

4.20.2 Map Indexed by Locations

Modules Lmap and Lmap_bitwise provide functors implementing maps indexed by locations and zones (respectively). The argument of these functors have to implement values attached to indices (resp. locations or zones).

These implementations are quite more complex than simple maps because they automatically handle overlaps of locations (or zones). So such implementations actually require that the structures implementing the values attached to indices are at least semi-lattices; see the corresponding signatures in module Lattice_type. For this purpose, functors of the abstract interpretation toolbox can help (see in particular module Abstract_interp).

4.21 GUI Extension

Prerequisite: *Knowledge of* Lablgtk2.

Each plug-in can extend the Frama-C graphical user interface (aka GUI) in order to support its own functionalities in the Frama-C viewer. For this purpose, a plug-in

developer has to register a function of type Design.main_window_extension_points \rightarrow unit thanks to Design.register_extension. The input value of type Design.main_window_extension_points is an object corresponding to the main window of the Frama-C GUI. It provides accesses to the main widgets of the Frama-C GUI and to several plug-in extension points. The documentation of the class type Design.main_window_extension_points is accessible through the source documentation (see Section 4.22).

The GUI plug-in code has to be put in separate files into the plug-in directory. Furthermore, in the Makefile, the variable PLUGIN_GUI_CMO has to be set in order to compile the GUI plug-in code (see Section 5.2.3).

Besides time-consuming computations have to call the function **!Db.progress** from time to time in order to keep the GUI reactive.

The GUI implementation uses Lablgtk2 [10]: you can use any Lablgtk2-compatible code in your gui extension. A complete example of a GUI extension may be found in the plug-in Occurrence (see file src/plugins/occurrence/register_gui.ml).

Potential issues All the GUI plug-in extensions share the same window and same widgets. So conflicts can occur, especially if you specify some attributes on a predefined object. For example, if a plug-in wants to highlight a statement s in yellow and another one wants to highlight s in red at the same time, the behavior is not specified but it could be quite difficult to understand for an user.

4.22 Documentation

Prerequisite: *Knowledge of* ocamldoc.

Here we present some hints on the way to document your plug-in. First Section 4.22.1 introduces a quick general overview about the documentation process. Next Section 4.22.2 focuses on the plug-in source documentation.

4.22.1 General Overview

Command make doc produces the whole Frama-C source documentation in HTML format. The generated index file is doc/code/html/index.html. A more general purpose index is doc/index.html (from which the previous index is accessible).

The previous command takes times. So command **make doc-kernel** only generates the kernel documentation (*i.e.* Frama-C without any plug-in) while **make \$(PLUGIN_NAME)_DOC** (by substituting the right value for **\$(PLUGIN_NAME)**) generates the documentation for a single plug-in.

4.22.2 Source Documentation

Each plug-in should be properly documented. Frama-C uses ocamldoc and so you can write any valid ocamldoc comments.

ocamldoc tags for Frama-C The tag @since version should document any element introduced after the very first release, in order to easily know the required version of the Frama-C kernel or specific plug-ins. In the same way, the Frama-C documentation generator provides a custom tag @modify version description which should be used to document any element which semantics have changed since its introduction.

Furthermore, the special tag **Qplugin developer guide** must be attached to each function used in this document.

Plug-in API A plug-in should export functions in its plug-in interface or through modules Db or Dynamic as explained in Section 4.9.

The interface name of a plug-in plugin must be Plugin.mli. Be careful to capitalization of the filename which is unusual in OCaml but required here for compilation purposes.

Internal Documentation for Kernel Integrated Plug-ins The Frama-C documentation generator also produces an internal plug-in documentation which may be useful for the plug-in developer itself. This internal documentation is available *via* file doc/code/plugin/index.html for each plug-in plugin. You can add an introduction to this documentation into a file. This file has to be assigned into variable PLUGIN_INTRO of the Makefile (see Section 5.2.3).

In order to ease access to this internal documentation, you have to manually edit the file doc/index.html in order to add an entry for your plug-in in the plug-in list.

Internal Documentation for External Plug-ins External plug-ins can be documented in the same way as plug-ins that are compiled together with Frama-C. However, in order to be able to compile the documentation with make doc, you must have generated the documentation of Frama-C's kernel (make doc, see above) and installed it with the make install-doc-code command.


4.22. DOCUMENTATION

Kind	Name	Specification	default
	PLUGIN	Plugins to be loaded with	from inout eva scope
Command		each subsequent run.	variadic for tests under
Command			./tests directory
	CMD	Program to run	./bin/toplevel.opt
	OPT	Options given to the pro-	-val -out -input -deps for
		gram	tests under ./tests directory
	STDOPT	Add and remove options	None
		from the default set	
	EXIT	Indicate expected exit sta- tus if not 0.	None
	LOG	Add an additional file to	None
	LOG	compare against an oracle	10000
	EXECNOW	Run a command before	None
		the following commands.	
		When specified in a con-	
		figuration file, run it only	
		once.	
	EXEC	Similar to EXECNOW, but	None
		run it once per testing file.	
	MACRO	Define a new macro	None
	FILTER	Command reading the	None
		standard input used to	
		filter results. In such a	
		command, the predefined	
		macro @PTEST_ORACLE@ is	
		set to the basename of the	
		oracle.	
	MODULE	Register a dynamic module	None
		to be built and to be loaded	
		with each subsequent test	
	TIMEOUT	kill the test after the given	None
		duration (in seconds of	
		CPU user time) and report	
		a failure	
	NOFRAMAC	empty the list of frama-c	None
		commands to be launched	
		(EXEC and EXECNOW direc-	
		tives are still executed).	
Test suite	DONTRUN	Do not execute this test	None
rest suite	FILEREG	selects the files to test	.*\.\(c i\)
Misc.	COMMENT	Comment in the configura-	None
IVIISC.		tion	
	GCC	Unused (compatibility	None
		only)	

Figure 4.2: Directives in configuration headers of test files.

Projects States	Project p_1	 Project p_n
AST a	value of a in p_1	 value of a in p_n
data d_1	value of d_1 in p_1	 value of d_1 in p_n
data d_m	value of d_m in p_1	 value of d_m in p_n

Figure 4.3: Representation of the Frama-C State.



Server = Project Library

Figure 4.4: Interaction between the project library and your registered global data.

Туре	Index
varinfo	vid
compinfo	ckey
enuminfo	ename
typeinfo	tname
stmt	sid
logic_info	l_var_info.lv_id
logic_var	lv_id
fieldinfo	fname and fcomp.ckey

Figure 4.5: Indices of AST nodes.

Chapter 5 Reference Manual

Target readers: Developers who would like to have a deep understanding of Frama-C.

This chapter is a reference manual for Frama-C developers. It provides details completing the previous chapters.

5.1 Configure.in

Figure 5.1 presents the different parts of configure.in in the order in which they are introduced in the file. The second column of the table indicates whether the given part might need to be modified by a kernel-integrated plug-in developer. More details are provided below.

Id	Name	Mod.	Reference
1	Configuration of make	no	
2	Configuration of OCaml	no	
3	Configuration of mandatory tools/libraries	no	
4	Configuration of non-mandatory tools/libraries	no	
5	Platform configuration	no	
6	Wished Frama-C plug-in	\mathbf{yes}	Sections $4.1.2$ and $4.1.4$
7	Configuration of plug-in tools/libraries	yes	Section $4.1.3$
8	Checking plug-in dependencies	\mathbf{yes}	Section $4.1.5$
9	Makefile creation	\mathbf{yes}	Section $4.1.2$
10	Summary	\mathbf{yes}	Section 4.1.2

Figure 5.1: Sections of configure.in.

- 1. Configuration of make checks whether the version of make is correct. Some useful option is -enable-verbosemake (resp. -disable-verbosemake) which set (resp. unset) the verbose mode for make. In verbose mode, full make commands are displayed on the user console: it is useful for debugging the makefile. In non-verbose mode, only command shortcuts are displayed for user readability.
- 2. Configuration of OCaml checks whether the version of OCaml is correct.
- 3. Configuration of other mandatory tools/libraries checks whether all the external mandatory tools and libraries required by the Frama-C kernel are present.

- 4. Configuration of other non-mandatory tools/libraries checks which external non-mandatory tools and libraries used by the Frama-C kernel are present.
- 5. Platform Configuration sets the necessary platform characteristics (operating system, specific features of gcc, *etc*) for compiling Frama-C.
- 6. Wished Frama-C Plug-ins sets which Frama-C plug-ins the user wants to compile.
- 7. Configuration of plug-in tools/libraries checks the availability of external tools and libraries required by plug-ins for compilation and execution.
- 8. Checking Plug-in Dependencies sets which plug-ins have to be disabled (at least partially) because they depend on others plug-ins which are not available (at least partially).
- 9. Makefile Creation creates Makefile.config from Makefile.config.in including information provided by this configuration.
- 10. Summary displays summary of each plug-in availability.

5.2 Makefiles

In this section, we detail the organization of the different Makefiles existing in Frama-C. First Section 5.2.1 presents a general overview. Next Section 5.2.2 details the different sections of Makefile.config.in, Makefile.common, Makefile.generic, Makefile.generating and Makefile. Next Section 5.2.3 introduces the variables customizing Makefile.dynamic. Finally Section 5.2.5 shows specific details of Makefile.dynamic.

5.2.1 Overview

Frama-C uses different Makefiles (plus the plug-in specific ones). They are:

- Makefile: the general Makefile of Frama-C;
- Makefile.generating: it contains the complex rules that generate files. It is not directly in the general Makefile in order to reduce the dependencies of these rules to Makefile.generating;
- Makefile.config.in: the Makefile configuring some general variables (especially the ones coming from configure);
- Makefile.common: the Makefile providing some other general variables;
- Makefile.generic: the Makefile providing generic rules for compiling source files
- .Makefile.plugin.generated: the Makefile introducing specific stuff for plug-in compilation which is generated from Makefile.plugin.template;
- Makefile.dynamic: the Makefile usable by plug-in specific Makefiles.
- Makefile.dynamic_config: this Makefile is automatically generated either from Makefile.dynamic_config.internal or Makefile.dynamic_config.external. It sets variables which automatically configure Makefile.dynamic.

- Makefile.clean contains specific targets for cleaning which are separated from Makefile for performance reasons.
- .Makefile.user is a per-user Makefile that can be used to override some variables. If it is not present, the default values of Makefile variables will be used.

Makefile and .Makefile.user are part of the root directory of the Frama-C distribution while the other ones are part of directory share. Each Makefile either includes or is included into at least another one. Figure 5.2 shows these relationships. Makefile




Figure 5.2: Relationship between the Makefiles

and Makefile.dynamic are independent: the first one is used to compile the Frama-C kernel while the second one is used to compile the Frama-C plug-ins. Their common variables are defined in Makefile.common (which includes Makefile.config.in). They also include Makefile.generic, that defines default compilation rules for various kinds of source files. Makefile.plugin.template defines generic rules and variables for compiling plug-ins. It is used to generate .Makefile.plugin.generated for each plugin.

CHAPTER 5. REFERENCE MANUAL

.Makefile.plugin.generated is included either by Makefile for kernel-specific plug-ins integrated in Frama-C Makefile and by Makefile.dynamic for plug-ins with their own Makefiles. .Makefile.user is included by Makefile when the former exists. It is only used when compiling Frama-C itself, and has no effect for external plugins.

5.2.2 Sections of Makefile, Makefile.generating, Makefile.config.in, Makefile.common and Makefile.generic

Figure 5.3 presents the different parts of Makefile.config.in, Makefile.common, Makefile.generic, Makefile.generating and Makefile in the order that they are introduced in these files. The third row of the tabular says whether the given part may be modified by a kernel-integrated plug-in developer. More details are provided below.

- 1. Working directories (split between Makefile.config.in and Makefile.common defines the main directories of Frama-C. In particular, it declares the variable FRAMAC_SRC_DIRS which should be extended by a plug-in developer if he uses files which do not belong to the plug-in directory (that is if variable PLUGIN_TYPES_CMO is set, see Section 5.2.3).
- 2. Installation paths defines where Frama-C has to be installed.
- 3. Ocaml stuff defines the OCaml compilers and specific related flags.
- 4. Libraries defines variables for libraries required by Frama-C.
- 5. Miscellaneous commands defines some additional commands.
- 6. Miscellaneous variables defines some additional variables.
- 7. Variables for plug-ins defines some variables used by plug-ins distributed within Frama-C (and using the configure of Frama-C).
- 8. Flags defines some variables setting compilation flags.
- 9. Verbosing sets how make prints the command. In particular, it defines the variable VERBOSEMAKE which must be set yes in order to see the full make commands in the user console. The typical use is
 - \$ make VERBOSEMAKE=yes
- 10. Shell commands sets all the shell commands eventually executed while calling make.
- 11. Command pretty printing sets all the commands to be used for pretty printing.

Example 5.1 Consider the following target foo in a plug-in specific Makefile.

foo: bar \$(PRINT_CP) \$@ \$(CP) \$< \$@

Executing

\$ make foo

prints

Id	Name	File	Mod.	Reference
1	Working directories	Makefile.config.in	no	
2	Installation paths	Makefile.config.in	no	
3	Ocaml stuff	Makefile.config.in	no	
4	Libraries	Makefile.config.in	no	
5	Miscellaneous commands	Makefile.config.in	no	
6	Miscellaneous variables	Makefile.config.in	no	
7	Variables for plug-ins	Makefile.config.in	no	
1 (bis)	Working directories	Makefile.common	no	
8	Flags	Makefile.common	no	
9	Verbosing	Makefile.common	no	
10	Shell commands	Makefile.common	no	
11	Command pretty printing	Makefile.common	no	
12	Tests	Makefile.common	no	
13	Generic rules	Makefile.generic	no	
14	Source files generation	Makefile.generating	no	
15	Global plug-in variables	Makefile	no	
16	Additional global variables	Makefile	no	
17	Main targets	Makefile	no	
18	Coverage	Makefile	no	
19	Ocamlgraph	Makefile	no	
20	Frama-C Kernel	Makefile	no	
21	Plug-in sections	Makefile	yes	Section 4.3
22	Generic variables	Makefile	no	
23	Toplevel	Makefile	no	
24	GUI	Makefile	no	
25	Standalone obfuscator	Makefile	no	
26	Tests	Makefile	no	
27	Emacs tags	Makefile	no	
28	Documentation	Makefile	no	
29	Installation	Makefile	yes	Not written yet.
30	File headers: license policy	Makefile	yes	
31	Makefile rebuilding	Makefile	no	
32	Cleaning	Makefile	no	
33	Depend	Makefile	no	
34	ptests	Makefile	no	
35	Source distribution	Makefile	no	

Figure 5.3: Sections of Makefile.config.in, Makefile.common and Makefile.

CHAPTER 5. REFERENCE MANUAL

Copying to foo

while executing

\$ make foo VERBOSEMAKE=yes

prints

| cp -f bar foo

If one of the two commands is missing for the target foo, either make foo or make foo VERBOSEMAKE=yes will not work as expected.

- 12. Tests defines a generic template for testing plug-ins.
- 13. Generic rules contains rules in order to automatically produces different kinds of files (*e.g.* .cm[iox] from .ml or .mli for OCaml files)
- 14. Source files generation contains rules for generating files that depend on the configuration and on which the main Makefile depends on. They are put in an auxiliary Makefile.generating to avoid unnecessary rebuilds.
- 15. Global plug-in variables declares some plug-in specific variables used throughout the makefile.
- 16. Additional global variables declares some other variables used throughout the makefile.
- 17. Main targets provides the main rules of the makefile. The most important ones are top, byte and opt which respectively build the Frama-C interactive, bytecode and native toplevels.
- 18. Coverage defines how compile the eponymous library.
- 19. Ocamlgraph defines how compile the eponymous library.
- 20. Frama-C Kernel provides variables and rules for the Frama-C kernel. Each part is described in specific sub-sections.
- 21. After Section "Kernel", there are several sections corresponding to **plug-ins** (see Section 5.2.3). This is the part that a plug-in developer has to modify in order to add compilation directives for its plug-in.
- 22. Generic variables provides variables containing files to be linked in different contexts.
- 23. Toplevel provides rules for building the files of the form bin/toplevel.*.
- 24. GUI provides rules for building the files of the form bin/viewer.*
- 25. Standalone obfuscator provides rules for building the Frama-C obfuscator.
- 26. Tests provides rules to execute tests. make tests takes care of generating the appropriate environment and launching ptests (see Section 4.5) for all test suites of the kernel and enabled plugins. It is possible to pass options to ptests through the PTESTS_OPTS environment variable.

- 27. Emacs tags provides rules which generate emacs tags (useful for a quick search of OCaml definitions).
- 28. Documentation provides rules generating Frama-C source documentation (see Section 4.22).
- 29. Installation provides rules for installing different parts of Frama-C.
- 30. File headers: license policy provides variables and rules to manage the Frama-C license policy.
- 31. Makefile rebuilding provides rules in order to automatically rebuild Makefile and configure when required.
- 32. Cleaning provides rules in order to remove files generated by makefile rules.
- 33. Depend provides rules which compute Frama-C source dependencies.
- 34. Ptests provides rules in order to build ptests (see Section 4.5).
- 35. Source distribution provides rules usable for distributing Frama-C.

5.2.3 Variables of Makefile.dynamic

Figures 5.4 and 5.5 presents all the variables that can be set before including Makefile.dynamic (see Section 4.4). Details are provided below.

• Variable PLUGIN_NAME is the module name of the plug-in.

This name must be capitalized (as is each OCaml module name). It must be distinct from all other visible modules in the plugin directory, or in the Frama-C kernel.

- Variable PLUGIN_DIR is the directory containing plug-in source files. It is usually set to src/plugins/plugin where plugin is the plug-in name.
- Variable PLUGIN_ENABLE must be set to yes if the plug-in has to be compiled. It is usually set to @plugin_ENABLE@ provided by configure.in where plugin is the plug-in name.
- Variable PLUGIN_HAS_META must be set to yes if plug-in *plugin* gets a META file describing its packaging. Unless PLUGIN_HAS_META is yes, the following variables are used to generate a suitable META:
 - PLUGIN_VERSION short text with *plugin* version number. Default value is Frama-C's version number.
 - PLUGIN_REQUIRES packages that must be loaded before the *plugin*. By default, there is no such package.
 - PLUGIN_DEPENDENCIES other plug-ins that must be loaded before the *plugin*. By default, there is no dependency.

Remark: the *plugin* package name is defined to be frama-c-*plugin* with lowercased plugin name. You can refer to it directly with ocamlfind.

Kind	Name	Specification
	PLUGIN_NAME	Module name of the plug-in
Plug-in	PLUGIN_DIR	Directory containing plug-in source files
Declaration	PLUGIN_ENABLE	Whether to compile the plug-in
Declaration	PLUGIN_HAS_META	Provided META (default: no)
	PLUGIN_DESCRIPTION	Short description (defaults to name)
Packaging	PLUGIN_VERSION	Version number (defaults to $Frama-C$'s)
(for META)	PLUGIN_DEPENDENCIES	Dependencies to other plug-ins
	PLUGIN_REQUIRES	Dependencies to ocamlfind packages
	PLUGIN_CMO	Object files (without .cmo)
Object Files	PLUGIN_CMI	Standalone interfaces (without .cmi)
Object Plies	PLUGIN_GUI_CMO	Additional objects files for the GUI
	PLUGIN_TYPES_CMO	External .cmo files
	PLUGIN_BFLAGS	Plug-in specific flags for ocamlc
	PLUGIN_OFLAGS	Plug-in specific flags for ocamlopt
Compilation	PLUGIN_EXTRA_BYTE	Additional bytecode files to link against
flags	PLUGIN_EXTRA_OPT	Additional native files to link against
	PLUGIN_EXTRA_DIRS	Additional directories containing source
		files, relative to the root directory of the
		plugin (i.e. PLUGIN_DIR)
	PLUGIN_LINK_BFLAGS	Plug-in specific flags for linking with
		ocamlc
	PLUGIN_LINK_OFLAGS	Plug-in specific flags for linking with
		ocamlopt
	PLUGIN_LINK_GUI_BFLAGS	Plug-in specific flags for linking a GUI
		with ocamlc
	PLUGIN_LINK_GUI_OFLAGS	Plug-in specific flags for linking a GUI
		with ocamlopt

Figure 5.4: Standard parameters of Makefile.dynamic.

- Variables PLUGIN_CMO and PLUGIN_CMI are respectively .cmo plug-in files and .cmi files without corresponding .cmo plug-in files. For each of them, do not write their file path nor their file extension: they are automatically added (\$(PLUGIN_DIR)/f.cm[io] for a file f).
- Variable PLUGIN_TYPES_CMO is the .cmo plug-in files which do not belong to \$(PLUGIN_DIR). They usually belong to src/plugins/plugin_types where plugin is the plug-in name (see Section 4.9.2). Do not write file extension (which is .cmo): it is automatically added.
- Variable PLUGIN_GUI_CMO is the .cmo plug-in files which have to be linked with the GUI (see Section 4.21). As for variable PLUGIN_CMO, do not write their file path nor their file extension.
- Variables of the form PLUGIN_*_FLAGS are plug-in specific flags for ocamlc, ocamlopt, ocamldep or ocamldoc.
- Variable PLUGIN_GENERATED is files which must be generated before computing plugin dependencies. In particular, this is where .ml files generated by ocamlyacc and ocamllex must be placed if needed.
- Variable PLUGIN_DEPENDS is the other plug-ins which must be compiled before the considered plug-in.

Using this variable is deprecated: you should consider to use PLUGIN_DEPENDENCIES instead.

- Variable PLUGIN_UNDOC is the source files for which no documentation is provided. Do not write their file path which is automatically set to \$(PLUGIN_DIR).
- Variable PLUGIN_TYPES_TODOC is the additional source files to document with the plugin. They usually belong to src/plugins/plugin_types where plugin is the plug-in name (see Section 4.9.2).
- Variable PLUGIN_INTRO is the text file to append to the plug-in documentation introduction. Usually this file is doc/code/intro_plugin.txt for a plug-in plugin. It can contain any text understood by ocamldoc.
- Variable PLUGIN_HAS_EXT_DOC is set to yes if the plug-in has its own reference manual. It is supposed to be a pdf file generated by make in directory doc/\$(PLUGIN_NAME)
- Variable PLUGIN_NO_TEST must be set to **yes** if there is no specific test directory for the plug-in.
- Variable PLUGIN_TESTS_DIRS is the directories containing plug-in tests. Its default value is tests/\$(notdir \$(PLUGIN_DIR))).
- Variable PLUGIN_TESTS_LIB contains the .ml plug-in specific files used by plug-in tests. Note that if you wish to have these files compiled before launching the tests (as opposed to e.g. compile them via an EXECNOW directive in a test file), you should add the corresponding .cmo and .cmxs files as pre-requisite of the \$(PLUGIN_DIR)/tests/ptests_config target.

Kind	Name	Specification	
	PLUGIN_DEPFLAGS	Plug-in specific flags for	
Dependencies		ocamldep	
	PLUGIN_GENERATED	Plug-in files to be generated be-	
		fore running ocamldep	
	PLUGIN_DEPENDS	Other plug-ins to be compiled be-	no
		fore the considered one	
	PLUGIN_DOCFLAGS	Plug-in specific flags for	
		ocamldoc	
Documentation	PLUGIN_UNDOC	Source files with no provided doc-	
		umentation	
	PLUGIN_TYPES_TODOC	Additional source files to docu-	
		ment	
	PLUGIN_INTRO	Text file to append to the plug-in	
		introduction	
	PLUGIN_HAS_EXT_DOC	Whether the plug-in has an exter-	
		nal pdf manual	
	PLUGIN_NO_TESTS	Whether there is no plug-in spe-	
		cific test directory	
—	PLUGIN_TESTS_DIRS	Directories containing tests	
Testing	PLUGIN_TESTS_DIRS_DEFAULT	tests to be included in the default	no
		test suite (all directories by de-	
		fault)	
	PLUGIN_TESTS_LIBS	Specific .ml files used by plug-in	
	DINGIN NO DEEANT TEOT	tests Whether to include tests in de-	
	PLUGIN_NO_DEFAULT_TEST	fault test suite.	
	PLUGIN_INTERNAL_TEST	Whether the test suite of the	
	I FORTH THIERMAR TEDI	plug-in is located in Frama-C's	
		own tests directory	
	PLUGIN_PTESTS_OPTS	Plug-in specific options to ptests	
	PLUGIN_DISTRIBUTED_BIN	Whether to include the plug-in in	no
Distribution	I FOOTW_DIDINIPOIED_DIN	binary distribution	
	PLUGIN_DISTRIBUTED	Whether to include the plug-in in	no
		source distribution	
	PLUGIN_DISTRIB_EXTERNAL	Additional files to be included in	no
		the distribution	
L			

Figure 5.5: Special parameters of Makefile.dynamic.

- Variable PLUGIN_NO_DEFAULT_TEST indicates whether the test directory of the plug-in should be considered when running Frama-C default test suite. When set to a non-empty value, the plug-in tests are run only through make \$(PLUGIN_NAME)_tests.
- Variable PLUGIN_INTERNAL_TEST indicates whether the tests of the plug-in are included in Frama-C's own tests directory. When set to a non-empty value, the tests are searched there. When unset, tests are assumed to be in the tests directory of the plugin main directory itself. Having the tests of a plugin inside Frama-C's own tests suite is deprecated. Plugins should be self-contained.
- Variable PLUGIN_PTESTS_OPTS allows to give specific options to ptests when running the tests. It comes in addition to PTESTS_OPTS (see 5.2.2§26). For instance, PLUGIN_PTESTS_OPTS:=-j 1 will deactivate parallelization of tests in case the plugin does not support concurrent runs.
- Variable PLUGIN_DISTRIB_BIN indicates whether the plug-in should be included in a binary distribution.
- Variable PLUGIN_DISTRIBUTED indicates whether the plug-in should be included in a source distribution.
- Variable PLUGIN_DISTRIB_EXTERNAL is the list of files that should be included within the source distribution for this plug-in. They will be put at their proper place for a release.

As previously said, the above variables are set before including Makefile.dynamic in order to customize its behavior. They must not be use anywhere else in the Makefile. In order to deal with this issue, for each plug-in p, Makefile.dynamic provides some variables which may be used after its inclusion defining p. These variables are listed in Figure 5.6. For each variable of the form p_VAR , its behavior is exactly equivalent to the value of the parameter PLUGIN_VAR for the plug-in p^1 .

5.2.4 .Makefile.user

The following variables can be set inside .Makefile.user:

• FRAMAC_PARALLEL: the contents of this variable are passed to ptests when it is called by Frama-C's Makefile. This variable can be used to override the default value of 4.

Example value: -j 6

• OCAML_ANNOT_OPTION: this variable of the Makefile can be overridden in .Makefile.user. By default, it is set to -annot -bin-annot. Users of Merlin do not need -annot.

Example value: -bin-annot

• FRAMAC_USER_FLAGS: the contents of this variable are passed to ocamlc and ocamlopt, *after* the standard configuration options coming from the Makefile. It can be used to tweak the warnings emitted by OCaml, and whether they are emitted as errors.

¹Variables of the form p_*CMX have no PLUGIN_*CMX counterpart but their meanings should be easy to understand.

 $^{^{2}}plugin$ is the module name of the considered plug-in (*i.e.* as set by $(PLUGIN_NAME)$).

Kind	Name ²	Remarks
Usual information	plugin_DIR	
	plugin_CMO	
	plugin_CMI	
Source files	plugin_CMX	
	$plugin_TYPES_CMO$	
	plugin_TYPES_CMX	
	$plugin_\texttt{TARGET_CMO}$	
	$plugin_\texttt{TARGET_CMX}$	
	plugin_target_cma	Empty if plug-in does not have exter- nal dependencies
Targets	$plugin_\texttt{TARGET_CMXA}$	Empty if plug-in does not have exter- nal dependencies
	plugin_TARGET_CMXS	Empty if plugin is not dynamic
	plugin_TARGET_GUI_CMO)
	plugin_TARGET_GUI_CMX	Empty if there is no plugin-
	plugin_TARGET_GUI_CMA	specific GUI code
	plugin_TARGET_GUI_CMXA	specific GOI code
	plugin_TARGET_GUI_CMXS	J
	plugin_BFLAGS	
	plugin_OFLAGS	
Compilation flags	plugin_LINK_BFLAGS	
compliation hags	plugin_LINK_OFLAGS	
	plugin_LINK_GUI_BFLAGS	
	plugin_LINK_GUI_OFLAGS	
Dependencies	plugin_DEPFLAGS	
Dependencies	plugin_GENERATED	
Documentation	plugin_DOCFLAGS	
	plugin_TYPES_TODOC	
Testing	plugin_TESTS_DIRS	
	plugin_TESTS_LIB	

Figure 5.6: Variables defined by Makefile.dynamic.

Example value: -warn-error -26-27 (do not consider warnings 26 and 27 as fatal errors)

• FRAMAC_USER_MERLIN_FLAGS: the contents of this variable are passed to a directive FLG, inside the .merlin file generated for Frama-C. (Through the merlin target of the main Makefile.) It can be used to tailor Merlin to your needs. See ocamlmerlin -help for the list of flags.

5.2.5 Makefile.dynamic

Not written yet: please report as "feature request" on http://bts.frama-c.com if you really need this section.

5.3 Ptests

5.3.1 Pre-defined macros for tests commands

Ptests pre-defines a certain number of macros for each test about to be run. Figure 5.7 gives their definition.

5.4 Profiling with Landmarks

Landmarks³ is a library for "quick and dirty" profiling of OCaml programs. It allows the insertion of annotations in the code to enable profiling of specific parts of it, but also an automatic mode, in which every function call is instrumented. The Frama-C configure file is setup to enable usage of this library when it is available (the usual way to install it is via the landmarks opam package).

For quick usage of the library:

- ensure that the configure script detected it (there should be a line checking for Landmarks... found);
- enable instrumentation when compiling Frama-C's files, that is, when running make, by setting the environment variable OCAML_LANDMARKS. For instance, to enable automatic instrumentation of every Frama-C function (note: this increases compilation time of Frama-C), run:
 - OCAML_LANDMARKS=auto make
- enable instrumentation *during execution* of Frama-C, again using OCAML_LANDMARKS. Note that the **auto** parameter here is implicit if you enabled it on the previous step. For instance, run:
 - OCAML_LANDMARKS= bin/frama-c [files] [options]

Commonly used options include output=landmarks.log to output the result to a file instead of stderr. Check https://github.com/LexiFi/landmarks for its documentation.

³https://github.com/LexiFi/landmarks

Name	Expansion		
frama-c	path to Frama-C executable		
PTEST_CONFIG	either the empty string or _ followed by the name of the		
	current alternative configuration (see section $4.5.3$).		
PTEST_DIR	current test suite directory		
PTEST_RESULT	current result directory		
PTEST_FILE	path to the current test file		
PTEST_NAME	basename of the current test file (without suffix)		
PTEST_NUMBER	rank of current test in the test file. There are in fact two in-		
	dependent numbering schemes: one for EXECNOW commands		
	and one for regular tests (if more than one OPT).		
PTEST_RESULT	shorthand alias to @PTEST_DIR@/result@PTEST_CONFIG@		
	(the result directory dedicated to the tested configuration)		
PTEST_ORACLE	basename of the current oracle file (macro only usable in		
	FILTER directives)		
PTEST_MODULE	current list of module defined by the MODULE directive		
PTEST_PLUGIN	current list of plugins defined by the PLUGIN directive		
PTEST_DEFAULT_OPTIONS	the default option list: -journal-disable -check		
	-no-autoload-plugins		
PTEST_LOAD_MODULE	the -load-module option related to the MODULE directive		
PTEST_LOAD_PLUGIN	the -load-module option related to the PLUGIN directive		
PTEST_LOAD_OPTIONS	shorthand alias to @PTEST_LOAD_PLUGIN@		
	@PTEST_LOAD_MODULE@		
PTEST_OPTIONS	the current list of options related to OPT and STDOPT direc-		
	tives (for CMD directives)		
frama-c	shortcut defined as follows: @frama-c-exe@		
	<pre>@PTEST_DEFAULT_OPTIONS@ @PTEST_LOAD_OPTIONS@</pre>		
frama-c-cmd	shortcut defined as follows: @frama-c-exe@		
	@PTEST_DEFAULT_OPTIONS@		
frama-c-exe	set to the value of the TOPLEVEL_PATH variable from		
	./tests/ptests_config file		

Figure 5.7:	Predefined	macros	for ptests	
-------------	------------	--------	------------	--

Appendix A Changes

This chapter summarizes the major changes in this documentation between each Frama-C release, from newest to oldest.

dev

• Testing: Document new directive PLUGIN and new predefined macros for ptests.

22.0 Titanium

• Testing: Document new directives TIMEOUT and NOFRAMAC

21.0 Scandium

• Configure: Documentation of configure_pkg, plugin_require_pkg and plugin_use_pkg macros.

20.0 Calcium

• Testing: Documentation of the new directive MODULE.

19.0 Potassium

- ACSL Extension: Document new status flag for registration functions
- Testing: Document usage of **@@** in a directive
- Profiling with Landmarks: New section

18.0 Argon

- Logging Services: Document error and failure behaviors.
- ACSL Extensions: New extension categories, for global and plain code annotations

Chlorine-20180501

• Logging Services: Introduction of warning categories

Sulfur-20171101

- **Tutorial**: Update and complete the Hello plug-in section along with making it available online.
- Testing: Explain the appropriate way to handle compilation of .ml scripts during tests
- Makefiles: Remove references to obsolete Makefile.plugin file

Phosphorus-20170501

- Makefiles: Update overview of Makefiles.
- ACSL Extensions: Update documentation after refactoring of ACSL extensions.
- Machine model: fully new section.

Silicon-20161101

• ACSL Extensions: Updated documentation for newly introduced loop extensions.

Aluminium-20160501

- Tutorial: Plugin Cfg renamed to ViewCfg; minor fixes.
- **Ptests**: Documentation of the new directive **EXEC**.
- Ptests: Documentation for sharing directives amongst ptests configurations
- Makefiles: Documentation for install:: target in dynamic plugins
- Makefiles: Documentation of exported TARGET_* variables
- Makefiles: Documentation of new option PLUGIN_EXTRA_DIRS
- Ptests: New option -gui

Magnesium-20151001

- License Policy: remove this section.
- Ptests: New configuration directive LOG and new macro PTEST_RESULT
- File Tree: remove this section, now subsumed by the new Chapter on Software Architecture and by the API documentation.
- File Tree Overview: remove this useless section.
- Software Architecture: rewrite the whole chapter.
- No more PLUGIN_HAS_MLI.

Sodium-20150201

- Type Library: document Datatype.Serializable_undefined.
- Command Line Options: document Parameter_sig.Kernel_function_set.
- Configure.in: warn about using Frama-C macros within conditionals
- Logical Annotations: document ACSL extended clauses mechanism (added section 4.19).
- Tutorial: fix hello_world.ml.

Neon-20140301

- Reference Manual: update list of main kernel modules.
- Logical Annotations: document module Property.
- Command Line Options: update according to kernel changes that split the module Plugin into several modules.
- Architecture, Plug-in Registration and Access and Reference Manual: document registration of a plug-in through a .mli file.
- Makefiles: introducing Makefile.generic.
- **Testing**: MACRO configuration directive.

Fluorine-20130601

- **Tutorial**: fully rewritten.
- Architecture and Reference Manual: remove references to Cilutil module.

Oxygen-20121001

- Makefile WARN_ERROR_ALL variable.
- Log: Debug category (~dkey argument).
- Visitor: DoChildrenPost action.
- Testing: document the need for directories to store result and oracles.
- Project Management System: Fine tuning of AST dependencies.
- Testing: added PTESTS_OPTS and PLUGIN_PTESTS_OPTS Makefile's variables.
- Type: document the type library.
- Logical Annotations: fully updated.
- Reference Manual: update kernel files.
- Testing: merge parts in Advanced Plug-in Development and in Reference Manual.
- Website: refer to CEA internal documentation.
- Command Line Options: explain how to modify the default behavior of an option.
- Command Line Options: fully updated.
- Project Management System: fully updated.
- Plug-in Registration and Access: Type replaced by Datatype and document labeled argument journalize.
- Configure.in: updated.
- Plug-in General Services: updated.
- Software Architecture: Type is now a library, not just a single module.

Nitrogen-20111001

- Tutorial of the Future: new chapter for preparing a future tutorial.
- Types as first class values: links to articles.
- **Tutorial**: kernel-integrated plug-ins are now deprecated.
- Visitors: example is now out-of-date.

Carbon-20110201

Unchanged.

Carbon-20101201-beta1

- Visitors: update example to new kernel API.
- **Documentation**: external plugin API documentation.
- Visitors: fix bug (replace DoChildrenPost by ChangeDoChildrenPost), change semantics wrt vstmt_aux.

Carbon-20101201-beta1

- Very Important Preliminary Warning: adding this very important chapter.
- Tutorial: fix bug in the 'Hello World' example.
- Testing: updated semantics of CMD and STDOPT directives.
- Initialization Steps: updated according to new options -then and -then-on and to the new 'Files Setting' stage.
- Visitors: example updated

We list changes of previous releases below.

Boron-20100401

- Configure.in: updated
- **Tutorial**: the section about kernel-integrated plug-in is out-of-date
- **Project**: no more **rehash** in datatypes
- Initialisation Steps: fixed according to the current implementation
- Plug-in Registration and Access: updated according to API changes
- **Documentation**: updated and improved
- Introduction: is aware of the Frama-C user manual
- Logical Annotations: fully new section
- Tutorial: fix an efficiency issue with the Makefile of the Hello plug-in

Beryllium-20090902

• Makefiles: update according to the new Makefile.kernel

Beryllium-20090901

- Makefiles: update according to the new makefiles hierarchy
- Writing messages: fully documented
- Initialization Steps: the different stages are more precisely defined. The implementation has been modified to take into account specificities of dynamically linked plug-ins
- Project Management System: mention value descr in Datatype
- Makefile.plugin: add documentation for additional parameters

Beryllium-20090601-beta1

- Initialization Steps: update according to the new implementation
- Command Line Options: update according to the new implementation
- Plug-in General Services: fully new section introducing the new module Plugin
- File Tree: update according to changes in the kernel
- Makefiles: update according to the new file Makefile.dynamic and the new file Makefile.config.in
- Architecture: update according to the recent implementation changes
- Tutorial: update according to API changes and the new way of writing plug-ins
- configure.in: update according to changes in the way of adding a simple plug-in
- Plug-in Registration and Access: update according to the new API of module Type

Lithium-20081201

- Changes: fully new appendix
- Command Line Options: new sub-section Storing New Dynamic Option Values
- Configure.in: compliant with new implementations of configure_library and configure_tool
- Exporting Datatypes: now embedded in new section *Plug-in Registration and Access*
- GUI: update, in particular the full example has been removed
- Introduction: improved
- Plug-in Registration and Access: fully new section
- **Project**: compliant with the new interface
- Reference Manual: integration of dynamic plug-ins

- Software architecture: integration of dynamic plug-ins
- **Tutorial**: improve part about dynamic plug-ins
- Tutorial: use Db.Main.extend to register an entry point of a plug-in.
- Website: better highlighting of the directory containing the html pages

Lithium-20081002+beta1

- **GUI**: fully updated
- **Testing**: new sub-section Alternative testing
- Testing: new directive STDOPT
- Tutorial: new section Dynamic plug-ins
- Visitor: ChangeToPost in sub-section Action Performed

Helium-20080701

- GUI: fully updated
- Makefile: additional variables of Makefile.plugin
- **Project**: new important note about registration of internal states in Sub-section *Internal State: Principle*
- Testing: more precise documentation in the reference manual

Hydrogen-20080502

- Documentation: new sub-section Website
- Documentation: new ocamldoc tag @plugin developer guide
- Index: fully new
- **Project**: new sub-section *Internal State: Principle*
- Reference manual: largely extended
- Software architecture: fully new chapter

Hydrogen-20080501

• First public release



Bibliography

- Patrick Baudin, Jean-Christophe Filliâtre, Thierry Hubert, Claude Marché, Benjamin Monate, Yannick Moy, and Virgile Prevosto. ACSL: ANSI C Specification Language. Version 1.8, March 2014.
- [2] Patrick Baudin and Anne Pacalet. Slicing plug-in. http://frama-c.com/slicing.html.
- [3] Loïc Correnson, Pascal Cuoq, Florent Kirchner, Armand Puccetti, Virgile Prevosto, Julien Signoles, and Boris Yakobowski. Frama-C User Manual, February 2015. http: //frama-c.com/download/frama-c-user-manual.pdf.
- [4] Loïc Correnson, Zaynah Dargaye, and Anne Pacalet. Frama-C's WP plug-in, February 2015. http://frama-c.com/download/frama-c-wp-manual.pdf.
- [5] Loïc Correnson and Julien Signoles. Combining Analysis for C Program Verification. In Formal Methods for Industrial Critical Systems (FMICS), August 2012.
- [6] Pascal Cuoq, Damien Doligez, and Julien Signoles. Lightweight Typed Customizable Unmarshaling. *ML Workshop'11*, September 2011.
- [7] Pascal Cuoq, Florent Kirchner, Nikolai Kosmatov, Virgile Prevosto, Julien Signoles, and Boris Yakobowski. Frama-C, A Program Analysis Perspective. In the 10th International Conference on Software Engineering and Formal Methods (SEFM 2012), volume 7504 of LNCS, pages 233–247. Springer, 2012.
- [8] Pascal Cuoq and Julien Signoles. Experience Report: OCaml for an industrial-strength static analysis framework. In *Proceedings of International Conference of Functional Programming (ICFP'09)*, pages 281–286, New York, NY, USA, September 2009. ACM Press.
- [9] Pascal Cuoq, Boris Yakobowski, and Virgile Prevosto. Frama-C's value analysis plug-in, February 2015. http://frama-c.com/download/frama-c-eva-manual.pdf.
- [10] Jacques Garrigue, Benjamin Monate, Olivier Andrieu, and Jun Furuse. LablGTK2. http://lablgtk.forge.ocamlcore.org.
- [11] Philippe Hermann and Julien Signoles. *Frama-C's RTE plug-in*, April 2013. http://frama-c.com/download/frama-c-rte-manual.pdf.
- [12] Florent Kirchner, Nikolai Kosmatov, Virgile Prevosto, Julien Signoles, and Boris Yakobowski. Frama-c: A software analysis perspective. *Formal Aspects of Computing*, pages 1–37, 2015. Extended version of [7].

BIBLIOGRAPHY

- [13] Xavier Leroy, Damien Doligez, Jacques Garrigue, Didier Rémy, and Jérôme Vouillon. The Objective Caml system. http://caml.inria.fr/pub/docs/manual-ocaml/index. html.
- [14] Donald Michie. Memo functions: a language feature with "rote-learning" properties. Research Memorandum MIP-R-29, Department of Machine Intelligence & Perception, Edinburgh, 1967.
- [15] Donald Michie. Memo functions and machine learning. Nature, 218:19–22, 1968.
- [16] George C. Necula, Scott McPeak, Shree Prakash Rahul, and Westley Weimer. CIL: Intermediate Language and Tools for Analysis and Transformation of C Programs. In *CC '02: Proceedings of the 11th International Conference on Compiler Construction*, pages 213–228, London, UK, 2002. Springer-Verlag.
- [17] Julien Signoles. Foncteurs impératifs et composés: la notion de projet dans Frama-C. In Hermann, editor, JFLA 09, Actes des vingtièmes Journées Francophones des Langages Applicatifs, volume 7.2 of Studia Informatica Universalis, pages 245–280, 2009. In French.
- [18] Julien Signoles. Une bibliothèque de typage dynamique en OCaml. In Hermann, editor, JFLA 11, Actes des vingt-deuxièmes Journées Francophones des Langages Applicatifs, Studia Informatica Universalis, pages 209–242, January 2011. In French.
- [19] Nicolas Stouls and Virgile Prevosto. Frama-C's Aoraï plug-in, April 2013. http://frama-c.com/download/frama-c-aorai-manual.pdf.

List of Figures

2.1	Plug-in Integration Overview.	15
2.2	Control flow graph for file test.c.	29
2.3	Control flow graph colored with reachability information.	32
2.4	CFG plug-in architecture	33
3.1	Frama-C Architecture Design.	42
4.1	ptests options	57
4.2	Directives in configuration headers of test files.	111
4.3	Representation of the Frama-C State	112
4.4	Interaction between the project library and your registered global data. \hdots .	112
4.5	Indices of AST nodes.	112
5.1	Sections of configure.in.	113
5.2	Relationship between the Makefiles	115
5.3	Sections of Makefile.config.in, Makefile.common and Makefile	117
5.4	Standard parameters of Makefile.dynamic	120
5.5	Special parameters of Makefile.dynamic.	122
5.6	Variables defined by Makefile.dynamic	124
5.7	Predefined macros for ptests	126



Index

.Makefile.plugin.generated, 114 .Makefile.user, 115, 116, 123 Abstract Interpretation, 44, 108 Abstract_interp, 108 Acsl_extension register_behavior, 104 register_code_annot, 104 register_code_annot_next_both, 104 register_code_annot_next_loop, 104 register_code_annot_next_stmt, 104 register_global, 104 Annotation, 99, 102 Annotations, 43, 102 add_assert, 101 Architecture, 41 Plug-in, 14AST, 78, 98, 99, 102 Copying, 100, 101 Modification, 45, 83, 99, 100 Sharing, see Sharing Ast add_monotonic_state, 81 get, 30, 77 mark_as_changed, 81 mark_as_grown, 81 self, 37, 83, 101 Boot, 88 Cabs, 44file, 90Cabs2cil convFile, 90 check_plugin, 46 Cil, 98, 99 cilVisitor, 98,99 behavior, 101 current_kinstr, 101 fill_global_tables, 100 get_filling_actions, 100, 101 vexpr, 101

vfile, 27 vglob, 99 vlogic_ctor_info_decl, 99 vlogic_ctor_info_use, 99 vlogic_info_decl, 99 vlogic_info_use, 99 vlogic_type_info_decl, 99 vlogic_type_info_use, 99 vlogic_var_decl, 99 vlogic_var_use, 99 voffs, 99 vstmt, 99 vvdec, 99 vvrbl, 99 copy_visit, 100, 101 dummyStmt, 75 get_kernel_function, 101 get_original_varinfo, 100 get_stmt, 101 get_varinfo, 100 inplace_visit, 100 lzero, 101 reset_behavior_varinfo, 100 set_varinfo, 100 visitAction, 99 ChangeDoChildrenPost, 100, 101 ChangeTo, 99, 101 ChangeToPost, 99 DoChildren, 28, 31, 99, 101 DoChildrenPost, 27, 28, 100 JustCopy, 28, 99, 101 JustCopyPost, 100 SkipChildren, 28, 99, 101 visitCilAstType, 99 visitCilFile, 99 visitCilFileCopy, 99 visitCilFileSameGlobals, 99 visitor_behavior, 100 Cil_datatype, 68 Fundec Hashtbl, 37

```
INDEX
```

Stmt equal, 68Hashtbl, 79 pretty, 68, 75 t, 75 ty, 75, 76 Varinfo, 79 Cil_state_builder, 78, 79 Stmt_hashtbl, 79 Cil_types, 43 acsl_extension, 104 acsl_extension_kind, 104 AExtended, 103 behavior, 103b_extended, 103 binop Div, 101 Mod, 101 compinfo, 100, 112 Dextended, 103 enuminfo, 100, 112 exp_node BinOp, 101 ext_category, 103 ext_code_annot_context, 103 fieldinfo, 100, 112 file, 90, 98-101 fundec, 31 GFun, 28 global, 99 logic_ctor_info, 99 logic_info, 99, 100, 112 logic_type_info, 99 logic_var, 99, 100, 112 mach, **90** offset, 99 relation Rneg, 101 stmt, 100, 112 stmtkind Block, 27 Break, 27 Continue, 27 Goto, 27 If, 27 Instr. 27 Loop, 27 Return, 27 Switch, 27

TryExcept, 27 TryFinally, 27 UnspecifiedSequence, 27typeinfo, 100, 112 varinfo, 79, 99, 100, 112 clean-install, 52 Cmdline, 87, 88 Exit, 89 is_going_to_load, 89 nop, **89** run_after_configuring_stage, 89 run_after_early_stage, 88 run_after_exiting_stage, 89 run_after_extended_stage, 80, 81, 88 run_after_loading_stage, 89 run_after_setting_files, 89 run_during_extending_stage, 88 stage Configuring, 89 Early, **88** Exiting, 89 Extended, 88 Extending, 88 Loading, 89 Command Line, 18, 29 -machdep, 91 -ocode, 67Option, 61, 84, 85 Parsing, 87 configure.ac, 49configure.in, **45**, **113** check_plugin, 47 check_plugin_dependencies, 50 configure_library, 47 configure_pkg, 47configure_tools, 47 ENABLE_plugin, 47 FORCE_plugin, **47** HAS_library, 48 HAS_OCAML_library, 48 LIB_SUFFIX, 48 OBJ_SUFFIX, 48 plugin_require, 49 plugin_require_external, 49 plugin_require_pkg, 48 plugin_use, 49 plugin_use_external, 49 plugin_use_pkg, 48 REQUIRE_plugin, 47

SELECTED_library, 48 $USE_plugin, 47$ Consistency, 45, 78, 84, 99, 100 Context Switch, 81, 84 CP, 116 Dataflow, 108 Datatype, **68**, 79, 81 Library, 67 Datatype, 67, 68 Bool, <u>38</u> bool, 68 char, 68func, 74, 76 func2, 68 func3, 76 Function, 71 identity, 69 Int, 70 int, 67, 68 List, 70, 71 list, 68 Make, 68-70 never_any_project, 69 Pair, 79Polymorphic, 70 Polymorphic2, 70 Polymorphic3, 70 Polymorphic4, 70 pp_fail, 70 Ref, 82 S, 68, 82 S_with_collections, 68 Serializable_undefined, 70, 75 String, 37, 68 Hashtbl, 70 Set, 68 string, 67, 68 Undefined, 70 undefined, 70unit, 74, 76 Db, 43, 73, 73, 74, 110 From.self, 80 Impact.compute_pragmas, 73 Main, 15extend, 14, 16, 17, 21, 23, 26, 61, 87, 89, 101 progress, 109 Properties, 103 Value

compute, 79, 83 get_stmt_state, 31 is_computed, 31, 39, 78, 83 is reachable, 31 self, 37, 79, 80, 84 Design, 15 main_window_extension_points, 109 register_source_selector, 32 register_extension, 32, 109 Documentation, **109**, 119 Kernel, 109 Plug-in, see Plug-in Documentation Source, 109 Tags, 110 Dot, 49 Dynamic, 15, 43, 74, 110 get, 74, 75, 76 Parameter, 86 Bool, 86 register, 74, 74, 75 Emitter, 85 Emitter create, 102, 103 Entry Point, 78 Entry point, 14 Equality Physical, 81, 82 Structural, 82 FCHashtbl, 43 File add_code_transformation_after_cleanup, 90add_code_transformation_before_cleanup, 90create_project_from_visitor, 101 init_from_c_files, 98 init_from_cmdline, 98 init_project_from_cil_file, 83, 98 init_project_from_visitor, 83, 98 must_recompute_cfg, 90 new_file_type, 90 new_machdep, 90 FRAMAC_INTERNAL, 52 FRAMAC_LIBDIR, 52 FRAMAC_SHARE, 19, 20, 22, 34, 51 FRAMAC_SRC_DIRS, 73, 116 From, 80, 81 From_parameters ForceCallDeps, 86 Frontc

add_syntactic_transformation, 90

Globals, 43 Functions get, 32 set_entry_point, 78 GnomeCanvas, 49 Gtk_helper graph_window, 32 GUI, 15, 108

Hashtable, 78, 79 Header, 119 Hello, 45 Highlighting, 109 Hook, 14

index.html, 109, 110 Initialization, 75, **87**, 88 install, 52 install-doc-code, 110

Journal, 15 Journalisation, 69 Journalization, 36, 74, 88, 89

Kernel, 41, 81, 118 Internals, 44 Services, 43 Kernel, 85 CodeOutput, 67 SafeArrays, 87 Unicode, 86 Kernel_function, 43, 79 dummy, 75 get_definition, 32 Make Table, 80, 81 pretty, 75 t, 75, 79ty, 75, 76 Kind, **80** Lablgtk, 48, 49, 109 Lablgtksourceview2, 48 Landmarks, 125 Lattice, 108 Lattice_type, 108 Library, 46 Configuration, 47, 113, 114 Dependency, 48 License, 119

Linking, 87, 88 Lmap, **108** Lmap_bitwise, 108 Loading, 78, 83, 89 Location, **107** Locations, 108 enumerate_valid_bits, 108 Location, 108 location, 108 Location_Bits, 108 Location_Bytes, 108 Zone, 108 Log add_listener, 65log_channel, 66 Messages, 61, 62abort, 63 debug, **63** error, 63failure. 63 fatal. 63 feedback, 62 log, **65** register_warn_category, 64 result, 62 set_warn_status, 64 verify, 63 warn_category, 64 warning, 63 with log, 65new_channel, 66 print_delayed, 67 print_on_output, 67 set_echo, 65 set_output, 67 with_log_channel, 66 Logging, see Messages Logic_const, 103 new_acsl_extension, 104 prel, 101 Logic_typing typing_context, 104 Logic_utils, 103 expr_to_term, 101 Machine model, 90 Makefile, 50, 109, 110, 114, 115, 115, 116 Makefile.clean, 115

Makefile.common, 114, 116

Makefile.config, 114

Makefile.config.in, 114, 115, 116 Makefile.dynamic, 15, 19, 20, 22, 34, **51**, 51, 72, 114, 115, 119 Makefile.dynamic_config, 114 Makefile.dynamic_config.external, 114 Makefile.dynamic_config.internal, 114 Makefile.generating, 114, 115, 116 Makefile.generic, 114, 116 Makefile.plugin.generated, 115 Makefile.plugin.template, 114 Marshaling, 69 memo, 79 Memoization, 77, 79, 80 Merlin, 123, 125 Messages, 61 Module Initialization, see Initialization Occurrence, 46, 109

Oracle, **53**, 54, 57

Parameter, 77 Parameter_customize, 87 set_negative_option_name, 87 Parameter_sig Bool, 85, 85 Builder, 85 Empty_string, 85 False, **85**, 85 Int, 85 Kernel_function_set, 85, 86 String, 85 String_set, 85 True, 85 Zero, 85 Int, 85 Kernel_function_set, 86 S, **85** Parameter_state get_selection, 84Parameters, 85 Pdg, 81 Platform, 114 Plug-in, 13, 43 Access, 74 API, 36, 74 Architecture, 14 Command Line Options, 18, 29 Compilation, 118 Configure, 36 Dependency, **46**, **46**, **49**, 114

Directory, 109, 119 Distribution, 123 Documentation, 24, 109, 109, 121 GUI, 15, 31, 49, 88, 108, 121 Initialization, see Initialization Kernel-integrated, 43, 113, 116 Access, 72 Registration, 72 Makefile, 19, 33 Messages, 17 Name, 119 Occurrence, see Occurrence Pdg, see Pdg Registration, 16, 74 Script, 15 Sparecode, see Sparecode Status, 46 Test, 121, 123 Testing, 22 Types, **73**, 121 Wished, 114 plugin types, 73 Plugin, 14, 15, 60 Register, 16, 17, 21, 25, 30, 43, 60, 61, 75, 85 PLUGIN_BFLAGS, 121 plugin_BFLAGS, 124 PLUGIN_CMI, **121** plugin_CMI, 124 PLUGIN_CMO, 19, 20, 22, 34, 51, 72, 121 *plugin_*CMO, **124** PLUGIN_DEPENDENCIES, 72, 119 PLUGIN_DEPENDS, 121 PLUGIN DEPFLAGS, 121 plugin_DEPFLAGS, 124 PLUGIN_DIR, 119 plugin_DIR, 124 PLUGIN_DISTRIB_BIN, 123 PLUGIN_DISTRIB_EXTERNAL, 123 PLUGIN_DISTRIBUTED, 123 PLUGIN_DOCFLAGS, 121 plugin_DOCFLAGS, 124 PLUGIN_ENABLE, 119 PLUGIN_EXTRA_BYTE, 121 PLUGIN_EXTRA_DIRS, 121 PLUGIN_EXTRA_OPT, 121 PLUGIN_GENERATED, 121 plugin_GENERATED, 124 PLUGIN_GUI_CMO, 34, 109, 121

plugin_GUI_OFLAGS, 124 PLUGIN_HAS_EXT_DOC, 121 PLUGIN_HAS_META, 119 PLUGIN_INTERNAL_TEST, 123 PLUGIN_INTRO, 110, 121 plugin_LINK_BFLAGS, 124 PLUGIN LINK GUI BFLAGS, 121 plugin_LINK_GUI_BFLAGS, 124 PLUGIN_LINK_GUI_OFLAGS, 121 PLUGIN_LINK_OFLAGS, 121 plugin_LINK_OFLAGS, 124 PLUGIN_NAME, 19, 20, 22, 34, 51, 72, 109, 119, 123PLUGIN_NO_DEFAULT_TEST, 123 PLUGIN_NO_TEST, 121 PLUGIN_OFLAGS, 121 plugin_OFLAGS, 124 PLUGIN_PTESTS_OPTS, 123 PLUGIN_REQUIRES, 119 plugin_TARGET_CMA, 124 plugin_TARGET_CMX, 124 plugin_TARGET_CMXA, 124 plugin_TARGET_CMXS, 124 plugin_TARGET_GUI_CMA, 124 plugin_TARGET_GUI_CMO, 124 plugin_TARGET_GUI_CMX, 124 plugin_TARGET_GUI_CMXA, 124 plugin_TARGET_GUI_CMXS, 124 plugin_TARGET_CMO, 124 PLUGIN_TESTS_DIRS, 22, 121 plugin_TESTS_DIRS, 124 PLUGIN_TESTS_LIB, 121 plugin_TESTS_LIB, 124 PLUGIN_TYPES_CMO, 74, 116, 121 plugin_TYPES_CMO, 124 plugin_TYPES_CMX, 124 PLUGIN_TYPES_TODOC, 121 plugin_TYPES_TODOC, 124 PLUGIN_UNDOC, 121 PLUGIN_VERSION, 119 Pretty_source PVDecl, 32Pretty_utils, 43 PRINT_CP, 116 Printer_api S.pp_exp, 27 S.pp_instr, 27 S.pp_stmt, 27 S.pp_varinfo, 28

Project, 37, 45, 69, 77, 98, 100 Current, 77, 78, 81, 83, 84, 100 Initial, 98 Use, **83** Project, 15, 83 clear, 39, 39, 83, 84 current, 77, 83 IOError, 83 load, 83 on, **84**, 84 save, 83set_current, 83, 83, 84 t, 39 Project_skeleton t, 83 Property, 103 Property_status, 103 Ptests, 22, 52, 119 PTESTS_OPTS, 118 Saving, 45, 78, 79, 83 Selection, 78, 84 self, **79** Session, 83 Sharing, 100, 101 Widget, 109 Side-Effect, 82, 87 Sparecode, 53 State, 77, 84, 85, 98, 99 Cleaning, 82, 84 Dependency, 78, 79, 81, 84 Postponed, **80**, 88 Functionalities, 78 Global Version, **81** Kind, see Kind Local Version, 81, 82 Name, 79, 81 Registration, 77-79 Selection, see Selection Sharing, 82 State, 80dummy, 80State_builder, 78, 79 Hashtbl, 37 Ref, 38, 82 Register, 78, 80, 81, 82 State_dependency_graph S.add_codependencies, 81 State_selection, 84 only_dependencies, 83

t, 39 with_dependencies, 39, 84 Structural_descr p_int, 69, 70 pack, 70structure $\operatorname{Sum}, 69, 70$ t Structure, 69, 70 Tags, 119 Test, 22, 52, 118 Configuration, 22, 54 Directive, 22, 54 CMD, 58, 111 COMMENT, **111** DONTRUN, 111 EXEC, 59, 111 EXECNOW, 59, 111 EXIT, **111** FILEREG, 59, 111 FILTER, 60, 111 GCC, **111** LOG, **111** MACRO, 59, 111 MODULE, 59, 111 NOFRAMAC, 111 OPT, 22, 55, 111 PLUGIN, **111** STDOPT, 58, 111 TIMEOUT, **111** Header, 22, 54, 56 Suite, **53**, 54 test_config, 54, 57, 59 tests, 53, 57 Tool, **46** Configuration, 47, 113, 114 Dependency, 48 Type Dynamic, 67 Value, 67, 74, 75 Type, 15 Abstract, 75, 76 AlreadyExists, 75 name, 70par, 69, 70 precedence Basic, 69 Call, 69 t, 67, 74, 75

Typed_parameter t, **85** VERBOSEMAKE, **51**, 116, 118 Visitor, 26, 98 Behavior, 100, 100 Cil, **98** Entry Point, 99 Copy, 83, 100, 101, 101 In-Place, **100**, 100 Visitor frama_c_inplace, 27 frama_c_visitor current_kf, 101 vglob_aux, 28, 99 vstmt_aux, 28, 31, 99 generic_frama_c_visitor, 98, 101 visitFramacFileSameGlobals, 30 visitFramacFunction, 38